

XMLmind DITA Converter Manual

Hussein Shafie

XMLmind Software
35, rue Louis Leblanc
78120 Rambouillet
France

Phone: +33 (0)9 52 80 80 37
ditac-support@xmlmind.com
www.xmlmind.com/ditac/

June 18, 2025

Table of Contents

List of Figures	ii
List of Tables	iii
Introduction	iv
Part I. Using XMLmind DITA Converter	1
Chapter 1. Installing XMLmind DITA Converter	2
1. Contents of the installation directory	3
Chapter 2. Getting started	6
1. Using the ditac command-line utility	6
Chapter 3. The ditac command-line utility	14
Chapter 4. XSLT stylesheets parameters	24
1. Page headers and footers	52
Chapter 5. Controlling the numbering of ordered lists	56
Chapter 6. Giving a background color to table cells	57
Chapter 7. Fancy code blocks	58
1. Syntax highlighting	60
Chapter 8. Rich media content	62
Part II. Customizing the output of XMLmind DITA Converter	69
Chapter 9. Simple customization	70
1. Customize the look of the (X)HTML pages generated by ditac	70
2. Customizing the look of the PDF files generated by ditac	71
Chapter 10. Using ditac to convert documents conforming to a DITA specialization	73
Chapter 11. Extensive customization	77
Part III. Embedding XMLmind DITA Converter in a Java™ application	84
Chapter 12. Recommended high-level embedding method	85
Chapter 13. Advanced low-level embedding method	87
Appendix A. About DITA support in XMLmind DITA Converter	92
Appendix B. Lightweight DITA support	94
1. XDITA support	94
2. HDITA support	94
3. MDITA support	96
3.1. Markdown extensions	98
Appendix C. Limitations and implementation specificities	111
Appendix D. Translating the messages generated by ditac	119
Index	i

List of Figures

1. XMLmind XSL Utility main window	iv
2-1. XMLmind XSL Utility main window	6
4-1. Page areas	51
4-2. Layout of a header	52
11-1. The intermediate files generated by the ditac preprocessor	77

List of Tables

2-1. Supported filename extensions 7

2-2. Supported output formats 10

B-1. Table caption here 108

Introduction

XMLmind DITA Converter (*ditac* for short) allows to convert the most complex DITA 1.0, 1.1, 1.2 and 1.3 documents to production-quality XHTML 1.0, XHTML 1.1, HTML 4.01, Web Help, HTML Help, Eclipse Help, EPUB, PDF, PostScript®, RTF (can be opened in Word 2000+), WordprocessingML (can be opened in Word 2003+), Office Open XML (.docx, can be opened in Word 2007+), OpenOffice (.odt, can be opened in OpenOffice/LibreOffice 2+).

The first part of this document explains how to install and use *ditac*. The target audience for this part is the DITA author.

The second part of this document explains how to customize the output of *ditac*. The target audience for this part is the DITA consultant.

The third part of this document explains how to embed *ditac* in a Java™ application. The target audience for this part is the Java™ programmer.

You'll find at the end of this document an appendix detailing the limitations and implementation specificities of *ditac*. Please refer to this appendix before posting support requests to the ditac-support+xmlmind.com, public, moderated, mailing list.




Tip

XMLmind DITA Converter has been integrated to [XMLmind XSL Utility](#), which is part of the [XMLmind XSL-FO Converter](#) commercial product.

Unlike **ditac**, which is a command-line utility, XMLmind XSL Utility is a graphical tool. It makes it easy parameterizing the DITA conversion process and then performing document conversions.

Figure 1. XMLmind XSL Utility main window



Moreover, this graphical tool comes in a Windows, auto-installable, self-contained, set-up .exe distribution⁽¹⁾ which includes [Apache FOP](#), [XMLmind XSL-FO Converter](#) and ditac.

If you just want to quickly and easily evaluate all the potential of ditac, you may want to download XMLmind XSL Utility Evaluation Edition from [XMLmind XSL-FO Converter web site](#). Do not be surprised because XMLmind XSL Utility Evaluation Edition generates output containing *random duplicate letters*. Of course, this does not happen with Professional Edition!

⁽¹⁾Of course, a .zip distribution is also available for platforms other than Windows.

Part I. Using XMLmind DITA Converter

How to install and run XMLmind DITA Converter (**ditac** for short). How to easily customize the output of **ditac**. Also learn about a number of nifty features you'll want to use. For technical writers.

Chapter 1. Installing XMLmind DITA Converter

Before you begin

XMLmind DITA Converter (*ditac* for short) requires using a Java™ 1.8+ runtime.

On Unix, make sure that the Java bin/ directory is referenced in the \$PATH and, at the same time, check that the Java runtime in the \$PATH has the right version:

```
$ java -version
openjdk version "24.0.1" 2025-04-15
OpenJDK Runtime Environment (build 24.0.1+9-30)
OpenJDK 64-Bit Server VM (build 24.0.1+9-30, mixed mode)
```

On Windows and on the Mac, this verification is in principle not needed as the **java** executable is automatically found in the \$PATH when Java has been properly installed.

Procedure

1. Unzip the distribution in any directory you want.

```
C:\> mkdir ditac
C:\> cd ditac
C:\ditac> unzip ditac-3_17_2.zip
C:\ditac> dir ditac-3_17_2
... <DIR> bin
... <DIR> doc
... <DIR> docsrc
...
```

XMLmind DITA Converter is intended to be used directly from the `ditac-3_17_2/` directory. That is, you can run the **ditac** command by simply executing (in a Command Prompt on windows, a terminal on Unix):

```
C:\ditac> ditac-3_17_2\bin\ditac
```

2. Depending the output formats you want to generate, you'll need to download and install third-party external tools.
 - If you want to generate PDF or PostScript®, download and install [Apache FOP](#). If your DITA document contain [MathML](#), you'll also want to install the [JEUclid FOP plug-in](#). This plug-in is needed to add MathML support to Apache FOP.

Alternatively, you may prefer to purchase [RenderX XEP](#) or [Antenna House Formatter](#). Note that [RenderX XEP Personal Edition](#) is free to use.



Tip

The `ditac-N_N_N-plus-fop.zip` distribution contains most recent [Apache FOP](#) (including hyphenation and [JEUclid](#)-based MathML support). This XSL-FO processor is automatically declared and thus, ready to be used to generate PDF or PostScript.

- If you want to generate RTF (can be opened in Word 2000+), WordprocessingML (can be opened in Word 2003+), Office Open XML (.docx, can be opened in Word 2007+) or OpenOffice (.odt, can be opened in OpenOffice/LibreOffice 2+), then you need to purchase [XMLmind XSL-FO Converter Professional Edition](#).

You can give XMLmind XSL-FO Converter a try by downloading Evaluation Edition from [XMLmind XSL-FO Converter web site](#). Do not be surprised because XMLmind XSL-FO Converter Evaluation Edition generates output containing *random duplicate letters*. Of course, this does not happen with Professional Edition!

- If you want to generate HTML Help, download and install the [HTML Help Workshop](#) (contains hhc.exe).
3. If you have installed any of the above external tools, you need now to instruct ditac where to find them. This can be done using the following command line options: **-fop**, **-xep**, **-ahf**, **-xfc**, **-hhc**. However, it is much more convenient to specify these command-line options once for all in a ditac.options file.

- a. Create ditac.options, a plain text file encoded using the native encoding of the platform (e.g. Windows-1252 on a Western Windows PC), in the ditac user preferences directory.

The ditac user preferences directory is:

- \$HOME/.ditac/ on Linux.
- \$HOME/Library/Application Support/XMLmind/ditac/ on the Mac.
- %APPDATA%\XMLmind\ditac\ on Windows. Example: C:\Users\john\AppData\Roaming\XMLmind\ditac\.

- b. Add the equivalent of a command-line option for each external tool installed in the preceding step. Use one or more newline characters to separate the options. More information in [The ditac.options file](#).

```
-fop E:\opt\fop\fop\fop.bat
-xfc E:\opt\xfc\bin\fo2rtf.bat
-hhc "C:\Program Files\HTML Help Workshop\hhc.exe"
```

1. Contents of the installation directory

bin/ditac, ditac.bat

Scripts used to run XMLmind DITA Converter (*ditac* for short). Use ditac on any Unix system. Use ditac.bat on Windows.

JAXP limits

This directory also contains file jaxp.properties which is referenced by the ditac scripts. As of Java™ version 24, the standard Java XML processing limits (*JAXP limits*) are very restrictive and no longer allow to load documents conforming to the DITA DTD. Therefore this file is needed to increase Java XML processing limits.

doc/index.html

Contains the documentation of ditac. *XMLmind DITA Converter Manual* is available in all the output formats supported by ditac. You'll also find there the reference manual of the API of ditac (generated by **javadoc**).

docsrc/manual/

Contains the DITA source of *XMLmind DITA Converter Manual*.

LEGAL/, LEGAL.txt

Contains legal information about ditac and about third-party components used in ditac.

lib/

All the (non-system) Java™ class libraries needed to run ditac:

ditac.jar

contains the code of XMLmind DITA Converter.

xmlresolver.jar

is [XMLResolver](#), an enhanced XML resolver with XML Catalog support.

relaxng.jar

is [Jing](#) version 20030619, James Clark's RELAX NG validator, slightly modified for use in [XMLmind XML Editor](#) and XMLmind DITA Converter. The details of the modifications are found in `LEGAL/relaxng.README`.

saxon12.jar

is Michael Kay's XSLT 3.0 engine. See <https://www.saxonica.com/>.

whcmin.jar**snowball.jar**

contains the code needed to run [XMLmind Web Help Compiler](#).

xslth1.jar

contains the code of the [XSLT syntax highlighting](#) open source software component.

flexmark.jar

[flexmark-java](#) is the software component used by ditac to parse Markdown and convert it to HTML.

plugin/

This directory is initially empty. It's the default location where user [plug-ins](#) are to be installed.

plus/

This directory is present only in the case of the `ditac-N_N_N-plus-fop.zip` distribution has been installed.

fop-N.N.M/

Contains most recent [Apache FOP](#), including hyphenation and [JEuclid](#)-based MathML support. This XSL-FO processor is automatically registered with ditac and thus, ready to be used to generate PDF or PostScript.

converters/

Contains a number of image converters based on [Batik](#), [JEuclid](#), [JLaTeXMath](#), etc. These image converters are automatically registered with ditac and thus, ready to be used to convert SVG to PNG, MathML to SVG or PNG, TeX/LaTeX math to SVG or PNG, etc.

schema/

Contains the DTD, RELAX NG and W3C XML schemas of DITA 1.3 1.2, 1.1, 1.0.1. File `schema/catalog.xml` contains an XML catalog which points to these local copies.

src/

Contains the Java source code of ditac. `src/build.xml` is an [ant](#) build file which allows to rebuild `lib/ditac.jar`.

whc_template/

Contains the template directory of [XMLmind Web Help Compiler](#).

xsl/

Contains the [XSLT 2.0](#) stylesheets used to convert DITA documents to a variety of formats.

fo/fo.xsl

Used to generate an intermediate XSL-FO file. After that, the XSL-FO file is converted to PDF , PostScript , RTF , WordprocessingML , Office Open XML (.docx) or OpenOffice/LibreOffice (.odt) by the means of an XSL-FO processor.

xhtml/xhtml.xsl

Used to generate XHTML 1.0 pages.

xhtml/xhtml1_1.xsl

Used to generate XHTML 1.1 pages.

xhtml/html.xsl

Used to generate HTML 4.01 pages.

xhtml/xhtml5.xsl

Used to generate XHTML 5 pages.

webhelp/webhelp.xsl

Used to generate Web Help containing XHTML 1 pages, which are then compiled using [XMLmind Web Help Compiler](#).

webhelp/webhelp5.xsl

Used to generate Web Help containing XHTML 5 pages, which are then compiled using [XMLmind Web Help Compiler](#).

htmlhelp/htmlhelp.xsl

Used to generate HTML Help files, which are then compiled using hhc.exe.

eclipsehelp/eclipsehelp.xsl

Used to generate Eclipse Help files.

epub/epub.xsl

Used to generate EPUB 2 files, which are then archived in a .epub file (Zip archive having a .epub extension).

epub/epub3.xsl

Used to generate EPUB 3 files, which are then archived in a .epub file (Zip archive having a .epub extension).

hdita/hdita.xsl

Translates XHTML5 to DITA according to the HDITA specification.

Chapter 2. Getting started

1. Using the ditac command-line utility

In this chapter, we'll explain how to run the **ditac** command-line utility by using examples. You'll find all the DITA input files used to run the following examples in the `ditac_install_dir/docsrc/manual/` directory.




Tip

XMLmind DITA Converter has been integrated to [XMLmind XSL Utility](#), which is part of the [XMLmind XSL-FO Converter](#) commercial product.

Unlike **ditac**, which is a command-line utility, XMLmind XSL Utility is a graphical tool. It makes it easy parameterizing the DITA conversion process and then performing document conversions.

Figure 2-1. XMLmind XSL Utility main window



Moreover, this graphical tool comes in a Windows, auto-installable, self-contained, set-up .exe distribution⁽²⁾ which includes [Apache FOP](#), [XMLmind XSL-FO Converter](#) and **ditac**.

If you just want to quickly and easily evaluate all the potential of **ditac**, you may want to download XMLmind XSL Utility Evaluation Edition from [XMLmind XSL-FO Converter web site](#). Do not be surprised because XMLmind XSL Utility Evaluation Edition generates output containing *random duplicate letters*. Of course, this does not happen with Professional Edition!

⁽²⁾Of course, a .zip distribution is also available for platforms other than Windows.

Converting a document to PDF

Converting a document, for example this manual, to PDF is done by executing the following command:

```
$ ditac -r manual_files out/manual.pdf manual.ditamap
```

The output directory `out/` is automatically created if it does not already exist.

The `-r manual_files` option is needed here only because this manual references audio and video files and also contains [TeX/LaTeX math](#). However, specifying this option (or `-resources` or `-i` or `-images`, which are all aliases of `-r`) is generally not needed when converting a DITA document to any of the XSL-FO based output formats (PDF, DOCX, ODT, etc).

Unless you have specified in the `ditac.options` file which XSL-FO processor to use, you'll have to execute:

```
$ ditac -fop /opt/fop/fop -r manual_files \
  out/manual.pdf manual.ditamap
```

or:

```
$ ditac -xep /opt/xep/xep -r manual_files \
  out/manual.pdf manual.ditamap
```

or:

```
$ ditac -ahf "C:\AHFv6\AHFCmd.exe" -r manual_files \
  out/manual.pdf manual.ditamap
```



Tip

No need to declare Apache FOP using the `-fop` command-line option if you have installed the distribution called `ditac-N_N_N-plus-fop.zip`. This distribution contains most recent [Apache FOP](#) (including hyphenation and MathML support). This XSL-FO processor is automatically registered with `ditac` and thus, ready to be used to generate PDF or PostScript.

The XSL-FO processors allowing to generate PDF also allows to generate PostScript®. Example:

```
$ ditac -r manual_files out/manual.ps manual.ditamap
```

Notice how the output format is determined by examining the filename extension of the output file.

Table 2-1. Supported filename extensions

Format	Extensions
XHTML 1.0	.html, .htm, .xhtml
EPUB 2	.epub
HTML Help	.chm
PDF	.pdf
PostScript®	.ps
RTF (can be opened in Word 2000+)	.rtf, .doc

Format	Extensions
WordprocessingML (can be opened in Word 2003+)	.wml, .xml
Office Open XML (can be opened in Word 2007+)	.docx
OpenOffice (can be opened in OpenOffice/LibreOffice 2+)	.odt

Note that **ditac** also allows to convert one or more topic files rather than a single map or bookmap file:

```
$ ditac -toc \
    out/draft.pdf embed1.dita embed2.dita
```

Ditac does not generate a table of contents (TOC) by default. Unless the input file is a bookmap containing an empty toc element in its frontmatter/booklists descendant element, you'll have to explicitly use the **-toc** option. Using the **-toc** option when the input file already specifies a TOC is harmless, so you could as well add a -toc line to your [ditac.options](#) file.

Converting a document to a word processor format

Converting a document to a word processor format just requires the use of an XSL-FO processor different from the one which generates PDF or PostScript. Fortunately all this automatically handled by **ditac**.

Convert a document to RTF (can be opened in Word 2000+):

```
$ ditac -r manual_files out/manual.rtf manual.ditamap
```

Unless you have specified in the [ditac.options](#) file which XSL-FO processor to use, you'll have to execute:

```
$ ditac -xfc /opt/xfc/fo2rtf -r manual_files \
    out/manual.rtf manual.ditamap
```

Suffice to specify the location of fo2rtf (fo2rtf.bat on Windows). Using this location, ditac infers the locations of fo2wml, fo2docx and fo2odt.



WARNING

[XMLmind XSL-FO Converter](#) Evaluation Edition ([download page](#)) generates output containing *random duplicate letters*. This makes this edition useless for any purpose other than evaluating XMLmind XSL-FO Converter. Of course, this does not happen with XMLmind XSL-FO Converter Professional Edition!

Convert a document to WordprocessingML (can be opened in Word 2003+):

```
$ ditac -xfc /opt/xfc/fo2wml -r manual_files out/manual.word.xml manual.ditamap
```

Convert a document to Office Open XML (can be opened in Word 2007+):

```
$ ditac -xfc /opt/xfc/fo2docx -r manual_files out/manual.docx manual.ditamap
```

Convert a document to OpenOffice (can be opened in OpenOffice.org 2+):

```
$ ditac -xfc /opt/xfc/fo2odt -v -p number all -r manual_files \
```

```
out/manual.odt manual.ditamap
```

Useful options

- `-v` instructs **ditac** to print progress messages on the console. Recommended when converting large documents.
- `"-p number all"` passes parameter "number" with value "all" to the XSLT stylesheets which generate the XSL-FO. The XSL-FO are then converted to OpenOffice format by the means of XMLmind XSL-FO Converter. The `number='all'` parameter instructs the XSLT stylesheets to number topics, tables and figures.

Converting a document to XHTML

Converting a document to multi-page XHTML 1.0 is done by executing the following command:

```
$ ditac -r manual_files -p xsl-resources-directory res \
  out/manual/_ .html manual.ditamap
```

- All the files generated by **ditac** are created in the `out/manual/` directory.
- `"-r manual_files"` instructs **ditac** to copy all the image, audio, video files referenced by the input DITA document to `out/manual/manual_files/`, possibly converting some image files from a non-supported format (e.g. TIFF) to a format supported by web browsers (e.g. PNG).



Remember

Specifying the `-r option` (or `-resources` or `-i` or `-images`, which are all aliases of `-r`) when generating an output format based on XHTML/HTML is needed in almost all the use cases.

- `"-p xsl-resources-directory res"` instructs **ditac** to copy all the resources needed by the XSLT stylesheets (CSS stylesheet, navigation icons, etc) to `out/manual/res/`.



Remember

Specifying a value for the `xsl-resources-directory` parameter when generating an output format based on XHTML/HTML is needed in almost all the use cases.

- Notice the strange name of the output file: `out/manual/_ .html`. In fact, this name is just used to specify the filename extension of the output files. The actual basenames of the output files are determined by examining the `chunk` and `copy-to` attributes possibly specified in the DITA map.

Note that a command-line like:

```
$ ditac -r manual_files -p xsl-resources-directory res \
  out/manual/foo.html manual.ditamap
```

works fine too. The only difference is that in such case, when a basename is needed and cannot be determined by examining the `chunk` and `copy-to` attributes specified in the DITA map, **ditac** will use

"foo" as a basename and you *may* end up having some output files called foo.html, foo-2.html, foo-3.html, etc. When the basename is specified as "_", it is the basename of the DITA map which is used. That is, you may have some output files called manual.html, manual-2.html, manual-3.html, etc.

What if you want to convert a document to HTML 4.01 or XHTML 1.1 or XHTML 5 rather than to XHTML 1.0? We have learned that there is no way to specify this using a [filename extension](#). The answer is: use the **-format** option (or **-f** in its short form). Example:

```
$ ditac -format html \
  -r manual_files -p xsl-resources-directory res \
  out/manual/_ .html manual.ditamap
```

Table 2-2. Supported output formats

Format	Name
XHTML 1.0	xhtml
XHTML 1.1	xhtml1.1
HTML 4.01	html
XHTML 5	xhtml5. html5 is an alias for xhtml5.
Web Help containing XHTML 1 pages	webhelp
Web Help containing XHTML 5 pages	webhelp5
HTML Help	htmlhelp
Eclipse Help	eclipsehelp
EPUB 2	epub
EPUB 3	epub3
PDF	pdf
PostScript®	ps
RTF (can be opened in Word 2000+)	rtf
WordprocessingML(can be opened in Word 2003+)	wml
Office Open XML (can be opened in Word 2007+)	docx
OpenOffice (can be opened in OpenOffice.org 2+)	odt
XSL-FO	fo

Useful options

- "-p [chain-pages](#) both". This XSLT stylesheet parameter specifies that a header and a footer containing navigation icons should be generated in order to link together all the HTML pages.
- "-p [chain-topics](#) yes". This XSLT stylesheet parameter specifies that navigation icons should be generated in order to link together all the topics.

- `-p default-table-width 100%`. Unless this XSLT stylesheet parameter is specified (or the `expand="page"` attribute is specified for all tables), web browsers tend to layout the generated HTML tables in order to make them as narrow as possible.

A full-fledged command-line is thus:

```
$ ditac -r manual_files -p xsl-resources-directory res \
  -p number all \
  -p chain-pages both \
  -p chain-topics yes \
  -p default-table-width 100% \
  out/manual/_html manual.ditamap
```

What if you want to generate a single XHTML page rather than multiple XHTML page? No need to create a new DITA map for that. Simply specify option `-chunk single` (or `-c` in its short form).

```
$ ditac -chunk single \
  -r manual_files -p xsl-resources-directory res \
  out/manual.html manual.ditamap
```

Converting a document to Web Help

Converting a document to Web Help is similar to converting a document to [multi-page XHTML 1](#). The main difference is that you need to explicitly specify `-format webhelp`:

```
$ ditac -format webhelp \
  -r manual_files -p xsl-resources-directory res \
  webhelp/_html manual.ditamap
```

If you prefer to generate Web Help containing XHTML 5 pages rather than XHTML 1 pages, then specify `-format webhelp5`.



Remember

Do not specify any of the following command-line options when generating Web Help: `-toc`, `-index`.

Converting a document to HTML Help

Converting a document to HTML Help is done by executing the following command:

```
C:\> ditac -r manual_files -p xsl-resources-directory res \
  out\manual.chm manual.ditamap
```

Unless you have specified in [the `ditac.options` file](#) the location of `hhc.exe`, you'll have to execute:

```
C:\> ditac -hhc "C:\Program Files\HTML Help Workshop\hhc.exe" \
  -r manual_files -p xsl-resources-directory res \
  out\manual.chm manual.ditamap
```

**Remember**

Do not specify any of the following command-line options when generating HTML Help:
-toc, -index.

Converting a document to Eclipse Help

Converting a document to [Eclipse Help](#) is similar to converting a document to multi-page XHTML. The main difference is that you need to explicitly specify `-format eclipsehelp`:

```
$ ditac -format eclipsehelp \
  -r manual_files -p xsl-resources-directory res \
  out/com.acme.widget.userguide/_html manual.ditamap
```

In order to deploy the generated Eclipse Help, you need to copy the output directory as a whole (`com.acme.widget.userguide/` in the case of the above example) to the `plugins/` directory of Eclipse and then use a text or XML editor to modify the generated `output_directory/plugin.xml`:

```
<plugin name="EDIT HERE: title of this help"
  id="EDIT HERE: unique.id.of.this.plugin"
  provider-name="EDIT HERE: author, company or organization"
  version="1.0.0">
  <extension point="org.eclipse.help.toc">
    <toc file="toc.xml" primary="true"/>
  </extension>
  <extension point="org.eclipse.help.index">
    <index file="index.xml"/>
  </extension>
</plugin>
```

If you do not want to hand edit `plugin.xml`, suffice to pass extra XSLT stylesheet parameters to `ditac`:

```
$ ditac -format eclipsehelp \
  -p plugin-name "ACME Widget User's Guide" \
  -p plugin-id com.acme.widget.userguide \
  -p plugin-provider "ACME Corp." \
  -r manual_files -p xsl-resources-directory res \
  out/com.acme.widget.documentation/_html manual.ditamap
```

**Remember**

If you want to see your document by selecting **Help** → **Help Contents** in Eclipse:

1. Do not specify any of the following command-line options when generating Eclipse Help: **-toc, -index.**
2. Parameter `plugin-id` is required to have the same value as the basename of the the output directory (`com.acme.widget.userguide/` in the case of the above example).
3. Copy this output directory to `eclipse_install_dir/dropins/` and not `eclipse_install_dir/plugins/`.

Converting a document to EPUB

Converting a document to [EPUB Help](#) is done by executing the following command:

```
$ ditac -r manual_files -p xsl-resources-directory res \
  out/manual.epub manual.ditamap
```

If you prefer to generate EPUB 3 rather than EPUB 2, then specify `-format epub3`.



Remember

Do not specify any of the following command-line options when generating EPUB: `-toc`.
Note that you may specify option `-index`.

Related information

- [Chapter 3. The `ditac` command-line utility](#)

Chapter 3. The ditac command-line utility

ditac [*option*]* *output_file* [*in_dita_file*]+

Command-line usage

Converts specified DITA input files to specified output file.

The input files must comprise a single map or bookmap file or possibly several, possibly multi-topic, topic files.

Example: convert the `userguide.ditamap` map to multi-page XHTML:

```
C:\docsrc> ditac -p center "fig table" ..\doc\userguide.htm userguide.ditamap
```

Example: convert the `introduction.dita` and `quickstart.dita` topics to PDF:

```
C:\docsrc> ditac draft1.pdf introduction.dita quickstart.dita
```

An input file may be specified using its URL or its filename.

The output directory is created if it does not already exist.

In some case, there is no need to specify a real output filename: the output directory and the extension of the output files suffice. In such case, specify "_" as the basename of the output file.

Example: convert `foo.ditamap` to multi-page XHTML. The XHTML pages must be generated in the `bar/` subdirectory.

```
C:\docsrc> ditac bar\_ .html foo.ditamap
```

In the above case, the basenames of the generated XHTML pages will be taken from the `@chunk` and `@copy-to` attributes specified in `foo.ditamap` if any, and from the basename of the map ("foo" in the case of our example) otherwise.

Commonly used command-line options

Some options have both a short name and a long name. Example: **-p** is equivalent to **-param**.

-p *param_name param_value*

-param *param_name param_value*

Specifies a conversion parameter, generally an XSLT stylesheet parameter. See [Chapter 4](#).

A *param_name* starting with "`load.doc_loader_name.`" specifies an option which is passed to the alternate document loader called *doc_loader_name*. For example, `-p load.mdita.autolink true` turns on the autolink extension in the [MDITA](#) loader. See [MDITA support](#).

-t *XSLT_stylesheet_URL_or_file*

-xslt *XSLT_stylesheet_URL_or_file*

Use the specified custom XSLT stylesheet rather than the stock one.

-c *none|single|auto*

-chunk *none|single|auto*

The "none" and "single" values may be used to force the generation of a single output file.

For example, `"-chunk single"` allows the reuse of a map designed to output multiple HTML pages in order to generate a PDF file.

For example, "-chunk none" allows the reuse of a map designed to output a PDF file in order to generate a single HTML page.

By default, the chunk mode is auto which means: generate a single output file (implicit "-chunk none") for formats such as pdf, ps, rtf, etc, and generate multiple output files for formats such as html, xhtml, webhelp, etc.

-f xhtml | xhtml1.1 | html | xhtml5 | html5 | webhelp | webhelp5 | epub | epub3 | htmlhelp | ps | pdf | rtf | odt | wml | docx | fo
-format xhtml | xhtml1.1 | html | xhtml5 | html5 | webhelp | webhelp5 | epub | epub3 | htmlhelp | ps | pdf | rtf | odt | wml | docx | fo

Explicitly specifies the output format. By default, the output format is determined using the extension of *output_file*.

Notes:

- A "htm" or "html" filename extension implicitly specifies an XHTML 1.0 output format, and not an HTML 4.01 output format. In order to generate HTML 4.01, explicitly specify "-f html". The same remark applies to xhtml1.1, xhtml5, webhelp, webhelp5.
- Option html5 is simply an alias for xhtml5.
- Option webhelp5 means Web Help containing XHTML 5 pages rather than XHTML 1 pages.
- Option epub specifies the EPUB 2 format.

-r resource_path | +
-resources resource_path | +
-i resource_path | +
-images resource_path | +

Copy (possibly converting between image formats if some [image converters](#) have been registered with **ditac**) the resource files, typically image files, referenced in the source topics to specified directory. If *resource_path* is relative, it is relative to the output directory.

Special value + (plus sign) means: copy, and possibly convert, resource files to an "automatic" *temporary directory*. This automatic temporary directory will be deleted after the conversion is complete. More information [below](#).

Note that "-r res" is equivalent to "-resourcehandler com.xmlmind.ditac.convert.ResourceProcessor res".



Remember

Unless option **-r**, **-resources**, **-i** or **-images** (or low-level option **-resourcehandler**) are used, *resources are neither copied nor converted*.



Remember

When generating any of the XSL-FO based output formats (PDF, DOCX, ODT, etc), specifying option **-r** (or any of its aliases: **-resources**, **-i**, etc) is generally not useful. Without option **-r**, the generated XSL-FO intermediate file will reference the image files using absolute URLs. This is not a problem as all XSL-FO-based output formats can embed a copy of these images. However, specifying option **-r** is really needed at least for the two following use cases:

- If your DITA document references audio or video files, specify **-r media** for example, to copy the audio or video files to a `media/` subdirectory created next to the output file.
- If your DITA document contains TeX/LaTeX math or if it contains MathML and the XSL-FO processor does not support MathML (e.g. RenderX [RenderX XEP](#)), specify **-r +** to let **ditac** invoke image converters. These image converters can convert TeX/LaTeX math and MathML to SVG, an image format supported by all XSL-FO processors.

-filter ditaval_URL_or_file

Apply specified conditional processing profile (`.ditaval` file) to the topics.

-attrvalues subject_scheme_map_URL_or_file

Specify an external subject scheme map. The controlled attribute values found in this subject scheme map are prepended to those loaded from the subject scheme maps possibly referenced in the map or bookmap to be converted.

-defaultattrvalues subject_scheme_map_URL_or_file

Same as **-attrvalues** except that the controlled attribute values found in this subject scheme map will *not* be used if some controlled attribute values are loaded from the subject scheme maps referenced in the map or bookmap to be converted.

-toc

Equivalent to `"-frontmatter toc"`.

Note that this option will *not* cause a **Table of Contents** to be generated when the map contains a single `<topicref>`⁽³⁾ having no `<topicref>` descendants.

-index

Equivalent to `"-backmatter indexlist"`.

-frontmatter spec

Automatically generate specified sections: **Table of Contents**, **List of Tables**, etc, before the other pages.

When used on a `<bookmap>`, this option adds elements *after* any existing `<booklists>` elements.

The syntax of *spec* is:

```
spec -> same_page [ ',' same_page ]*
same_page -> section [ '+' section ]*
section -> 'toc'|'figurelist'|'tablelist'|'examplelist'|
          'equationlist'|'indexlist'
```

Example: generate the **Table Of Contents** in its own page, followed by another page containing both the **List of Figures** and the **List of Tables**.

```
-frontmatter toc,figurelist+tablelist
```

⁽³⁾Not counting `<topicref>`s contained in `<frontmatter>` and `<backmatter>`.

-backmatter spec

Automatically generate specified sections: **Table of Contents**, **List of Tables**, etc, after the other pages. See **-frontmatter** for more information.

When used on a <bookmap>, this option adds elements *before* any existing <booklists> elements.

-addindex

When an output file contains the **Table of Contents** (let's call this file main.html) and when no file called index.html has been generated, this option copies main.html to index.html. Applies to formats: xhtml, xhtml1.1, html, webhelp.

-lang language_code

Specifies the main language of the document

Shorthand for:

```
-foconverter pdf "executable_file"
-foconverter ps "executable_file"
```

. Examples: "fr", "fr-CA". Needed to sort the index entries.

By default, this information is taken from the @xml:lang attribute of the root element of the topic map (if any, "en" otherwise).

-v**-vv****-vvv**

Turn verbosity on. More Vs means more verbose.

-o options_URL_or_file**-option options_URL_or_file**

This option lets the user specify a text file containing command-line arguments. This text file has the same format as [the ditac.options file](#).

Example:

```
$ ditac -v -o html.options foo.htm foo.ditamap
```

If html.options contains:

```
-format html
-p css http://www.acme.com/css/acme.css
```

then this is equivalent to running:

```
$ ditac -v -format html -p css http://www.acme.com/css/acme.css \
foo.htm foo.ditamap
```

Command-line options used to configure ditac

-ahf executable_file

Specifies the location of AHFCmd.exe (run.sh on platforms other than Windows).

Shorthand for:

```
-foconverter AHF pdf '"executable_file" -x 3 -p @PDF -d "%I" -o "%O"'
-foconverter AHF ps '"executable_file" -x 3 -p @PS -d "%I" -o "%O"'
```

-ahfconf configuration_file

Specifies the location of an [Antenna House Formatter configuration file](#). A relative file path is relative to the current working directory. Ignored unless option **-ahf** is also specified.

-fop executable_file

Specifies the location of the fop shell script (fop.bat on Windows).

Shorthand for:

```
-foconverter FOP pdf '"executable_file" -q -r -fo "%I" -pdf "%O"'
-foconverter FOP ps '"executable_file" -q -r -fo "%I" -ps "%O"'
```

-fopconf configuration_file

Specifies the location of an [Apache FOP configuration file](#). A relative file path is relative to the current working directory. Ignored unless option **-fop** is also specified.

**Remember**

XSL-FO converters last registered with **ditac** have priority over first registered ones.

However, no matter the order of command-line options, XSL-FO converters registered using low-level option **-foconverter** always have priority over those registered using options **-fop**, **-xep**, **-ahf**, **-xfc**, which in turn always have priority over bundled XSL-FO converters (such as the [Apache FOP](#) XSL-FO processor contained in *ditac-N_N_N-plus-fop.zip* distributions).

-foconverter processor_name target_format command

Register specified XSL-FO converter with **ditac**, a lower-level alternative to using **-xep**, **-fop**, **-ahf** or **-xfc**. Example:

```
-foconverter XFC rtf '/opt/xfc/bin/fo2rtf "%I" "%O"'
```

Note that this option can be specified several times with different values in the same command-line.

This low-level option may be used for example to specify a [configuration file for Apache FOP](#):

```
-foconverter FOP pdf \
'/opt/fop/fop -c /home/john/docs/fop.conf -q -r -fo "%I" -pdf "%O"'
```

**Remember**

XSL-FO converters last registered with **ditac** have priority over first registered ones.

However, no matter the order of command-line options, XSL-FO converters registered using low-level option **-foconverter** always have priority over those registered using options **-fop**, **-xep**, **-ahf**, **-xfc**, which in turn always have priority over bundled XSL-FO converters (such as the [Apache FOP](#) XSL-FO processor contained in *ditac-N_N_N-plus-fop.zip* distributions).

-hhc *exe_file*

Specifies the location of `hhc.exe`, the HTML Help compiler.

-imageconverter *input_file_extensions output_file_extensions command*

Register external image converter with **ditac**. Example:

```
-imageconverter .wmf.emf .svg \
'/opt/inkscape/bin/inkscape --export-type=svg -l -o "%I" "%O"
```

**Remember**

Image converters last registered with **ditac** have priority over first registered ones.

Note that image converters registered using option **-imageconverter** always have priority over bundled image converters (such as the stock `javax.imageio.ImageIO` based image converter and the [Batik](#), [JEuclid](#) and [JLaTeX-Math](#) image converters contained in *ditac-N_N_N-plus-fop.zip* distributions).

-plugin *plugin_name*

Use the DTDs/schemas and the XSLT stylesheets found in the plug-in subdirectory having specified name preferably to those found in *ditac_install_dir/schema/* and in *ditac_install_dir/xsl/*. See [What is a plug-in?](#).

-resourcehandler *class_name parameters*

Pass the resource files, typically image files, referenced in the source topics to *class_name*, a Java™ class implementing interface `com.xmlmind.ditac.preprocess.ResourceHandler`. String *parameters* is used to configure the newly created `ResourceHandler`.

Note that **-i images** is equivalent to **-resourcehandler com.xmlmind.ditac.convert.ResourceProcessor images**.

-xep *executable_file*

Specifies the location of the xep shell script (`xep.bat` on Windows).

Shorthand for:

```
-foconverter XEP pdf '"executable_file" -quiet -valid -fo "%I" -pdf "%O"'
-foconverter XEP ps '"executable_file" -quiet -valid -fo "%I" -ps "%O"'
```

-xfc *executable_file*

Specifies the location of the `fo2rtf` shell script (`fo2rtf.bat` on Windows).

Suffice to specify the location of `fo2rtf`. Using this location, **ditac** infers the locations of `fo2wml`, `fo2docx` and `fo2odt`.

Shorthand for:

```
-foconverter XFC rtf '"fo2rtf_executable_file" -rtf.target=MSWord "%I" "%O"'
-foconverter XFC wml '"fo2wml_executable_file" "%I" "%O"'
-foconverter XFC docx '"fo2docx_executable_file" "%I" "%O"'
-foconverter XFC odf '"fo2odt_executable_file" "%I" "%O"'
```

**WARNING**

XMLmind XSL-FO Converter Evaluation Edition ([download page](#)) generates output containing *random duplicate letters*. This makes this edition useless for any purpose other than evaluating XMLmind XSL-FO Converter. Of course, this does not happen with XMLmind XSL-FO Converter Professional Edition!

Command-line options used to debug ditac

-preprocess

Stop after preprocessing input files.

-automap save_file

Save the automatically generated topic map (if any) to specified file.

-keepfo

When generating PDF, RTF, etc, do not delete the temporary XSL-FO file.

-errout

Output all messages, including errors and warnings, to stdout.

-ignoreoptionsfile

Do not load the `ditac.options` options file. See below [The ditac.options file](#).

-validate

Validate *all* the XML files loaded by **ditac**. Any validation error will cause **ditac** to immediately stop running. Therefore the combination of the **-validate** and **-dryrun** options gives you a simple way to thoroughly check your DITA document.

Note that for the **-validate** option to work, *all* the XML files (maps, topics, even `.ditaval` filter files) loaded by **ditac** must start with the proper `<!DOCTYPE>` declaration.

This option is unrelated to [attribute value validation](#) by the means of subject scheme maps. When the map to be converted (or any of its submaps) references some subject scheme maps then the attribute value validation is automatic and cannot be turned off.

-dryrun

Use **ditac** as a validator, and most notably check cross-references. That is, do not generate any file; just report errors if any .

-version

Print version number and exit.

The ditac.options file

It is also possible to specify command-line options in the `ditac.options` options file. The content of this plain text file, encoded in the native encoding of the platform (e.g. Windows-1252 on a Western Windows PC), is automatically loaded by **ditac** each time this command is executed. The content of this file, command-line options separated by whitespace, is *prepended* to the options specified in the command-line.

Example: If `ditac.options` contains:

```
-v -p number all
```

Running:

```
~/docsrc$ ditac -p center "fig table" ../doc/userguide.htm userguide.ditamap
```

is equivalent to running:

```
~/docsrc$ ditac -v -p number all -p center "fig table" \
  ../doc/userguide.htm userguide.ditamap
```

The `ditac.options` options file is found in the `ditac` user preferences directory. This directory is:

- `$HOME/.ditac/` on Linux.
- `$HOME/Library/Application Support/XMLmind/ditac/` on the Mac.
- `%APPDATA%\XMLmind\ditac\` on Windows. Example: `C:\Users\john\AppData\Roaming/XMLmind\ditac\`.

The `ditac.options` options file is mainly useful to configure `ditac` once for all by specifying values for the **-fop**, **-fopconf**, **-xep**, **-xfc**, **-hhc**, **-plugin** and **-imageconverter** options.

Example:

```
-v
-xep E:\opt\xep\xep.bat
-fop E:\opt\fop\fop\fop.bat
-xfc E:\opt\xfc\bin\fo2rtf.bat
-hhc "C:\Program Files\HTML Help Workshop\hhc.exe"
```



Remember

- Relative filenames found in this file are relative to the current working directory, and not to the `ditac.options` options file. Therefore it is recommended to always specify absolute filenames.
- No comments (e.g. lines starting with '#') are allowed in `ditac.options`. Options must be separated by whitespace.
- In the above example, FOP is declared *after* XEP. This implies that it is FOP and not XEP, which will be used by `ditac` to generate PDF and PostScript®.
- An XSL-FO processor tend to consume a lot of memory. If the DITA conversion fails with an out-of-memory error, you need to edit the `xep` (`xep.bat`), `fop` (`fop.bat`), `fo2xxx` (`fo2xxx.bat`) scripts in order to increase the maximum amount of memory that the Java™ runtime may allocate. This is done by using the **-Xmx** option of the Java™ command-line. Example: `"java ... -Xmx512m ..."`.
- Starting from Java™ 1.6.0_23, converting XML documents to PDF using RenderX XEP randomly fails with false XSL-FO errors (e.g. attribute "space-before" may not be empty). This problem seems specific to the 64-bit runtime.

The workarounds for the above bug ("renderx #22766") are:

- Use a 32-bit Java™ runtime.
- OR Use a 64-bit Java™ runtime older than 1.6.0_23.
- OR Specify option **-valid** in the **xep** command-line. Note that this workaround is automatically used when you specify which RenderX XEP executable to use by the means of the **-xep** command-line option.

What is a plug-in?

A plug-in is simply a subdirectory of *ditac_install_dir/plugin/*. For example, *ditac_install_dir/plugin/MyPlugin/*.

This subdirectory may contain an [XML catalog file](#). This XML catalog file must be named `catalog.xml`. In the case of a DITA specialization, `catalog.xml` points to local copies of customized DTDs. Example: *ditac_install_dir/plugin/MyPlugin/catalog.xml*:

```
<catalog xmlns="urn:oasis:names:tc:entity:xmlns:xml:catalog"
  prefer="public">
  <public publicId="-//OASIS//DTD DITA Concept//EN"
    uri="dtd/concept.dtd"/>
  ...
</catalog>
```

This subdirectory may contain an `xsl/` subdirectory organized *exactly* like *ditac_install_dir/xsl/*. That is, this `xsl/` subdirectory may contain one or more of the following XSLT stylesheets:

XSLT stylesheet	Description
<code>xsl/fo/fo.xml</code>	Used to generate an intermediate XSL-FO file. After that, the XSL-FO file is converted to PDF , PostScript , RTF , WordprocessingML , Office Open XML (.docx) or OpenOffice/LibreOffice (.odt) by the means of an XSL-FO processor.
<code>xsl/xhtml1/xhtml1.xml</code>	Used to generate XHTML 1.0 pages.
<code>xsl/xhtml1/xhtml1_1.xml</code>	Used to generate XHTML 1.1 pages.
<code>xsl/xhtml1/html.xml</code>	Used to generate HTML 4.01 pages.
<code>xsl/xhtml1/xhtml15.xml</code>	Used to generate XHTML 5 pages.
<code>xsl/webhelp/webhelp.xml</code>	Used to generate Web Help containing XHTML 1 pages, which are then compiled using XMLmind Web Help Compiler .
<code>xsl/webhelp/webhelp5.xml</code>	Used to generate Web Help containing XHTML 5 pages, which are then compiled using XMLmind Web Help Compiler .
<code>xsl/htmlhelp/htmlhelp.xml</code>	Used to generate HTML Help files, which are then compiled using <code>hhc.exe</code> .
<code>xsl/eclipsehelp/eclipsehelp.xml</code>	Used to generate Eclipse Help files.
<code>xsl/epub/epub.xml</code>	Used to generate EPUB 2 files, which are then archived in a .epub file (Zip archive having a .epub extension).
<code>xsl/epub/epub3.xml</code>	Used to generate EPUB 3 files, which are then archived in a .epub file (Zip archive having a .epub extension).

When **ditac** is passed command-line option **-plugin *plugin_name***, it will use the DTDs/schemas and the XSLT stylesheets found in the plug-in subdirectory having specified name preferably to those found in *ditac_install_dir/schema/* and in *ditac_install_dir/xsl/*.

**Tip**

If you don't want your plug-ins to reside inside *ditac_install_dir/plugin/*, you may specify an alternate parent directory by the means of the `DITAC_PLUGIN_DIR` environment variable. Example:

- On Windows:

```
C:\>set DITAC_PLUGIN_DIR=C:\Users\john\ditac_plugins
```

- On Unix:

```
$ export DITAC_PLUGIN_DIR=/home/john/ditac_plugins
```

Related information

- [Chapter 4. XSLT stylesheets parameters](#)

Chapter 4. XSLT stylesheets parameters

Parameters common to all stylesheets



Note

- Parameters marked using this icon  are *system parameters*. They are automatically specified by the application executing the XSLT stylesheets. Such system parameters must not be specified by the end-user. Such system parameters are documented here only because the end-user may see them referenced in some configuration files.
- Parameters marked using this icon  are *pseudo-parameters*. They may or may not be passed to the XSLT stylesheets, but the important thing to remember is that they are also interpreted by ditac itself. By consequence, you cannot specify them in an XSLT stylesheet which customizes the stock ones (as explained in [Part II, Chapter 9, Section 2](#)).

Parameter	Value	Description
appendix-number-format	Allowed values are: 'I', 'i', 'A', 'a', '1'. Default value: 'A'.	The number format of topics referenced in a bookmap as appendix. By default, such topics are numbered as follows: Appendix A. Title of first appendix , Appendix B. Title of second appendix , etc.
cause-number-format	Allowed values are: 'I', 'i', 'A', 'a', '1'. Default value: 'A'.	In a <troubleshooting> topic, multiple <remedy> elements having no title are given numbers formatted using this format.
center	List of element names separated by whitespace. Example: 'fig equation-figure simpletable table'. Default value: ''.	Specifies which elements are to be centered horizontally on the page.
 ditacListsURI	URL ⁽⁴⁾ . Default value: <i>output_dir/ditac_lists.ditac_lists</i> .	The URL of file ditac_lists.ditac_lists.
equation-number-after	String. Default value: ') '.	Text added after the contents of a <equation-number> element.

⁽⁴⁾Unlike a filename, an URL must contain properly quoted characters. For example, do not specify 'Hello world.htm', instead specify 'Hello%20world.htm'.

Parameter	Value	Description
equation-number-before	String. Default value: ' ('.	Text added before the contents of a <equation-number> element.
extended-toc	Allowed values are: 'frontmatter', 'backmatter', 'both', 'none'. Default value: 'none'.	Allows to add <frontmatter> and <backmatter> <topicref>s to the Table of Contents (TOC) of a document. Note that the @toc, @navtitle, @locktitle, etc, attributes are applied normally to <frontmatter> and <backmatter> <topicref>s when an extended TOC is generated.
external-resource-base	Allowed values are: '', an URL ending with "/" or '#REMOVE'. Default value: '#REMOVE' for EPUB 2 and EPUB 3, '' for all the other output formats.	Specifies how to resolve <xref> or <link> elements having an <i>external</i> @scope attribute and a <i>relative</i> @href attribute. Example of such <xref> elements: <xref scope="external" format="java" href="src/Test.java">Test.java</xref>. '' Do not resolve the @href attribute. In this case, the external resource files are expected to be copied "by hand" to the output directory. An URL ending with "/" This URL is prepended to the value of the @href attribute. '#REMOVE' The <xref> or <link> element is processed as if it did not have an @href attribute.
highlight-source	Allowed values are: 'yes' and 'no'. Default value: 'yes'.	Allows to turn off syntax highlighting in elements specializing <pre>. By default, syntax highlighting is turned on for all elements specializing <pre> and having an @outputclass attribute equals to language-c, language-cpp, language-csharp, language-delphi, language-ini, language-java, language-javascript, language-m2, language-perl, language-php, language-python, language-ruby, language-tcl.
index-range-separator	String. Default value: '–' (EN DASH).	The string used to separate the first page number from the last page number in a page range of an indexed term. Example: index-range-separator='<- ->': C Cat 54, 87<- ->90

Parameter	Value	Description
link-auto-text	List of values separated by whitespace. Allowed values are: 'number' and 'text'. Default value: 'number text'.	This parameter specifies which text to generate for a <link> element, when this <link> element has no <linktext> child element or when this <linktext> child element is empty. Similar to above parameter xref-auto-text but for <link> elements.
note-icon-list	List of type attribute values separated by whitespace. Default value: 'attention caution danger fastpath important note notes remember restriction tip'.	Specifies the type (attribute @type) of the <note> elements for which icons should be used rather than text in order to represent note labels. Ignored unless use-note-icon='yes'.
number	List of values separated by whitespace. Allowed values are: 'topic', 'table', 'fig', 'equation-figure', 'all'. Default value: '' (number nothing).	Specifies which elements are to be numbered. 'all' is a short form for 'topic table fig equation-figure'. 'chapter-only' means: number topics, but only those referenced in a bookmap as <part>, <chapter> and <appendix>.  Note Please note that 'all' does not include 'example'. If you want to number all formal elements including examples, then you must specify 'all example'.
number-separator1	String. Default value: '.'.	The string used to separate the hierarchical number of topics acting as sections.
number-separator2	String. Default value: '-'.	The string used to separate the hierarchical number of figures, tables, examples and equations. When possible, the number of figure, table, example or equation is made relative to the number of the ancestor chapter or appendix. This gives for example (for descendants of chapter 5): Figure 5-1. Title of first figure of chapter 5 , Figure 5-2. Title of second figure of chapter 5 , etc.
mark-important-steps	Allowed values are: 'yes' and 'no'. Default value: 'no'.	Generates a "Required" (respectively "Optional") label for <step> and <substep> elements having

Parameter	Value	Description
		an <code>@importance</code> attribute set to "required" (resp. "optional").
part-number-format	Allowed values are: 'I', 'i', 'A', 'a', '1'. Default value: 'I'.	The number format of topics referenced in a bookmap as part. By default, such topics are numbered as follows: Part I. Title of first part , Part II. Title of second part , etc.
prepend-chapter-to-section-number	Allowed values are: 'yes' and 'no'. Default value: 'no'.	Normally topics which are descendants of chapters (that is, topics referenced in a bookmap as <code><chapter></code>) are numbered as follows: 1. Title of first section , 1.1. Title of first subsection , etc. Specifying <code>prepend-chapter-to-section-number='yes'</code> prepends the number of the chapter ancestor to the section number. This gives for example (for descendants of chapter 5): 5.1. Title of first section , 5.1.1. Title of first subsection , etc.
remedy-number-format	Allowed values are: 'I', 'i', 'A', 'a', '1'. Default value: 'A'.	In a <code><troubleshooting></code> topic, multiple <code><remedy></code> elements having no title are given numbers formatted using this format.
show-draft-comments	Allowed values are: 'yes' and 'no'. Default value: 'no'.	Specifies whether <code><draft-comments></code> elements should be rendered.
troubleSolution-number-format	Allowed values are: 'I', 'i', 'A', 'a', '1'. Default value: '1'.	In a <code><troubleshooting></code> topic, multiple <code><troubleSolution></code> elements having no title are given numbers formatted using this format.
title-after	List of element names separated by whitespace. Example: 'fig equation-figure table'. Default value: ''.	Specifies which elements should have their titles displayed after their bodies.
title-page	Allowed values are: 'auto', 'none' or the URI of a custom title page. Default value: 'auto'.	Specifies the kind of "title page" (contains the title of the document, its author, etc) to be generated before the actual contents of the document. 'auto' Automatically generate a title page based on the title and metadata of the map. 'none' Do not generate a title page.

Parameter	Value	Description
		URI of a custom title page Specifies the URI of a custom title page. If the URI is relative, it is relative to the current working directory of the user. This custom title page is an XHTML file for XHTML-based formats (XHTML, HTML Help, etc). This custom title page is an XSL-FO file for FO-based formats (PDF, RTF, etc). Such custom title pages are generally hand-written. - The child nodes of the body element of the custom XHTML title page are wrapped in a <code>div</code> contained in the XHTML/HTML file being generated by the XSLT stylesheet. Do not add a <code><!DOCTYPE></code> to such custom XHTML title page because otherwise, the XSLT stylesheet may fail loading it. See sample custom XHTML title page. - The child nodes of the first <code>fo:flow[@flow-name='xsl-region-body']</code> element of the custom XSL-FO title page are wrapped in a <code>fo:block</code> contained the XSL-FO file being generated by the XSLT stylesheet. See sample custom XSL-FO title page.
title-prefix-separator1	String. Default value: ' . '.	The string used to separate the number of an formal object from its title.
use-note-icon	Allowed values are: 'yes' and 'no'. Default value: 'no'.	Specifies whether icons should be used rather than text in order to represent the label of a <code><note></code> element.
watermark-image	URI. If the URI is relative, it is relative to the current working directory of the user. No default value.	Specifies an image file which is to be used as a watermark in all the pages comprising the output document. See also parameter watermark .

Parameter	Value	Description
xref-auto-text	List of values separated by whitespace. Allowed values are: 'number' and 'text'. Default value: 'number'.	This parameter specifies which text to generate for an <code><xref></code> element, when this <code><xref></code> element contains no text at all⁽⁵⁾. Let's suppose that an <code><xref></code> element containing no text at all points to a topic titled "Installation". Because the <code><xref></code> element points to an element having a <code><title></code> child element, ditac may use this title as a starting point for the generated text. Now let's suppose that topics are numbered and that the number of the "Installation" topic is "Chapter 5". The text generated for this <code><xref></code> element is thus: If <code>xref-auto-text='number'</code> Chapter 5 If <code>xref-auto-text='text'</code> Installation If <code>xref-auto-text='number text'</code> Chapter 5. Installation Note that this specification is just a hint because ditac needs anyway to generate some text. For example, if topics are not numbered and <code>xref-auto-text='number'</code>, the generated text will be "Installation". For XSL-FO based output formats, see also parameter show-xref-page.
★xsl-re-sources-directory	URL. A relative URL is relative to the output directory. Default value: 're-sources/' resolved against the directory which contains the XSLT stylesheets.	Most XSLT stylesheets generate files which reference resources such as icons or CSS stylesheets. This parameter specifies the target directory which is to contain such resources. If this directory does not exist, it is automatically created. If this directory does not already contain the resources needed by the XSLT stylesheets, such resources are automatically copied to this directory. The default value of this parameter is something like <code>file:/opt/ditac/xsl/xhtml/re-sources/</code> for the stylesheets generating XHTML. URL <code>file:/opt/ditac/xsl/xhtml/re-sources/</code> specifies an existing directory containing <code>basic.css</code>, <code>note.png</code>, <code>important.png</code>, etc.

⁽⁵⁾This implies that the `xref-auto-text` parameter is ignored when an `<xref>` element contains some text.

Parameter	Value	Description
		This means that by default, no directory is created and no resource is copied. If the value of this parameter is an absolute URI, then ditac assumes that no resource directory is to be created and no resource is to be copied because this has already been done by the user.  Important • Explicitly specifying something like <code>xsl-resources-directory='res'</code> is almost <i>always required</i> when generating files having an XHTML/HTML based format (XHTML, HTML Help, etc). • Explicitly specifying something like <code>xsl-resources-directory='res'</code> is almost <i>never required</i> when generating files converted from XSL-FO (PDF, RTF, etc).

Parameters common to the stylesheets that basically generate XHTML or HTML

This applies to the stylesheets that generate XHTML, HTML, Web Help, HTML Help, Eclipse Help, EPUB.

Parameter	Value	Description
add-copiable-links	List of values separated by whitespace. Allowed values are: 'topic', 'table', 'fig', 'equation-figure', 'example', 'section', 'all' (equivalent to 'topic table fig equation-figure example section'). Default value: '' (do not add copiable links).	Adds a <i>copiable link</i> to the <title> child elements of specified “formal elements”. • If the “formal element” is numbered (e.g. has a "Chapter 1." automatically generated label), then the automatically generated label is converted to a link. This link points to the formal element (e.g. a link to the <topic> having a chapter role). • Otherwise (e.g. a <section> which cannot be numbered), a link containing the section symbol, "\$", is added to the <title>. This link points to the formal element (e.g. a link to the <section>).

Parameter	Value	Description
		This automatically generated link to a formal element is intended to be copied using the "Copy Link" entry found in the contextual menu of all web browsers in order to be shared with others. For example, send this link by email.  Restriction - For this facility to work, the formal element must have an @id attribute, whether specified by the author or automatically generated by ditac. - This parameter is ignored when generating HTML Help, Eclipse Help and EPUB.
add-index-toc	Allowed values are: 'yes' and 'no'. Default value: 'yes'.	Specifies whether an A-Z list should be added at the beginning of the back-of-the-book index.
chain-pages	Allowed values are: 'none', 'top', 'bottom' or 'both'. Default value: 'none'.	Specifies whether a header and/or a footer containing navigation icons should be generated in order to link together all the HTML pages.  Note There is no need to specify a value other than 'none' when generating Web Help, HTML Help, Eclipse Help and EPUB.
chain-topics	Allowed values are: 'yes' and 'no'. Default value: 'no'.	Specifies whether navigation icons should be generated in order to link together all the topics. See also related parameter: ignore-navigation-links.  Note There is no need to specify a value other than 'no' when generating Web Help,

Parameter	Value	Description
		HTML Help, Eclipse Help and EPUB.
css	URL. Default value: ''.	Low-level parameter specifying which CSS stylesheet to use to style the generated (X)HTML pages. When neither <code>css</code> nor <code>custom-css</code> is specified, the default CSS stylesheet being used is <code>xsl-resources-directory/base.css</code>.  Restriction Not supported by the stylesheets that generate EPUB.
cssResourceName	URL basename relative to the directory specified by parameter <code>xsl-resources-directory</code> . Default value: 'base.css'.	Very low-level parameter specifying which CSS stylesheet to use. This CSS stylesheet is expected to be found in the resources directory.  Note This parameter is not useful unless you develop a plug-in implementing a DITA specialization. More information in Part II, Chapter 10.
★custom-css	URL. Default value: ''.	Specifies the custom CSS stylesheet used to style the generated (X)HTML pages. This high-level parameter has priority over low-level parameter <code>css</code>. This custom CSS stylesheet is copied to directory <code>xsl-resources-directory</code>. Therefore <code>custom-css</code> requires directory <code>xsl-resources-directory</code> to be specified as an URL which is relative to the output directory (e.g. <code>xsl-resources-directory='res'</code>). How to use <code>custom-css</code> is explained in Part II, Chapter 9, Section 1.
default-table-width	A percentage, typically something like '100%' or '90%'. Default value: '' (as narrow as possible).	The default width of <code><table></code> and <code><simplatable></code> elements.

Parameter	Value	Description
external-link-icon-height	Length. A length may have a unit. Default is px. Default value: '10'.	The height of the “opens in new window” icon.
external-link-icon-name	Basename. Default value: 'new_window.png'.	The basename of the “opens in new window” icon. This icon is found in the resources directory.
external-link-icon-width	Length. A length may have a unit. Default is px. Default value: '10'.	The width of the “opens in new window” icon.
format-to-type	Zero or more DITA format/MIME type pairs. Example: "txt text/plain xml application/xml html-text/html". Default value: '', which means that DITA xref/@format is <i>not</i> converted to XHTML a/@type.	Allows to map DITA xref/@format to XHTML a/@type. Using default empty value, <xref scope="external" format="txt" href="http://acme.com/info.xyz"> is converted to . The fact that file extension ".xyz" is unknown may cause problems when attempting to navigate or download file "info.xyz" using a Web browser. If -p format-to-type "txt text/plain" is passed to ditac then <xref scope="external" format="txt" href="http://acme.com/info.xyz"> is converted to , which is better.
generator-info	String Default value: 'XMLmind DITA Converter VERSION'.	The name of the software which has been used to create the HTML pages. Specify an empty string if you don't want to have a <meta name="generator" content="XXX"/> element added to your HTML pages.
ignore-navigation-links	Allowed values are: 'yes', 'no' and 'auto'. Default value: 'auto' for XHTML and its variants; 'yes' for Web Help, HTML Help, Eclipse Help and EPUB	If 'yes', do not generate the navigation links corresponding to topicref attribute @collection-type. If 'no', generate the navigation links corresponding to topicref attribute @collection-type. If 'auto', generate the navigation links corresponding to topicref attribute @collection-type, unless chain-topics=yes .
javascripts	String. List of URLs separated by whitespace.	The URLs specified in this parameter must point to JavaScript files. These URLs are converted

Parameter	Value	Description
	Default value: ''.	to <script> XHTML elements added to the <html>/<head> elements of the XHTML files generated by ditac. Note that an URL may end with ';async', ';defer' or a combination of both flags. These flags are translated to the corresponding attributes of the <script> element. Example: <pre>https://cdn.jsdelivr.net/npm/mathjax@3/es5/tex-mml-chtml.js;async</pre> is translated to: <pre><script type="text/javascript" src="https://cdn.jsdelivr.net/npm/mathjax@3/es5/tex-mml-chtml.js" async="async"></script></pre>
mathjax	Allowed values are: 'yes', 'no' and 'auto'. Default value: 'no'.	MathJax is a JavaScript display engine for mathematics that works in all browsers. Though a number of web browsers natively support embedded MathML, it's recommended to specify parameter <code>mathjax=yes</code> or <code>mathjax=auto</code> to let MathJax render embedded MathML found in the generated XHTML 5 and XHTML 5 Web Help files. 'yes' Add a <script> XHTML element loading MathJax to the <html>/<head> elements of all XHTML files generated by ditac. 'auto' Same as 'yes', but add <script> only to generated XHTML files containing MathML and/or TeX/LaTeX math. Ignored by all XHTML-based formats but XHTML and Web Help.
mathjax-url	String. Default value: the URL pointing to a MathJax CDN, as recommended in the MathJax documentation.	The URL allowing to load the MathJax engine configured for rendering MathML. Ignored unless parameter <code>mathjax</code> is set to 'yes' or 'auto'.
mark-external-links	Allowed values are: 'yes' and 'no'. Default value: 'no'.	Specifies whether an external link should be marked using a “opens in new window” icon.
navigation-icon-height	Length. A length may have a unit. Default is px.	The height of a navigation icon.

Parameter	Value	Description
	Default value: '16'.	
navigation-icon-suffix	String. Default value: '.png'.	The suffix of a navigation icon. The root names of navigation icons are fixed: first, first_disabled, last, last_disabled, next, next_disabled, previous, previous_disabled, parent, parent_disabled, child, child_disabled. For example, if note-icon-suffix='.svg', the default resources directory is expected to contain first.svg, first_disabled.svg, last.svg, etc. In principle, there is no need for an end-user to specify any of the navigation-icon-suffix, navigation-icon-width or navigation-icon-height parameters.
navigation-icon-width	Length. A length may have a unit. Default is px. Default value: '16'.	The width of a navigation icon.
screen-resolution	Positive integer. Default value: '96'.	The resolution of the screen in dot per inch (DPI). This resolution is used to convert image dimensions such as 3cm to pixels.
xhtml-mime-type	A MIME type without a parameter such as 'text/html', 'application/xhtml+xml', 'application/xml' or the empty string (''). Default value: see prose.	Low-level parameter. Do not change default value unless you know what you are doing. - Specify 'text/html' to serve XHTML as HTML. This is the default value for all (X)HTML-based output formats except for EPUB 2 and (X)HTML5. - Specify 'application/xhtml+xml' if you prefer to serve XHTML as XML. This is the default value for EPUB 2. - Specify an empty string if you prefer not to generate <meta http-equiv="Content-Type">. This is the default value for (X)HTML5 for which a <meta charset="UTF-8"> is generated instead.

Parameters common to the stylesheets that generate HTML Help, Eclipse Help and EPUB

Parameter	Value	Description
add-toc-root	Allowed values are: 'yes' and 'no'. Default value: 'yes'.	If 'yes', add a pseudo TOC entry, bearing the title of the document, containing all the actual TOC entries.  Restriction - Value 'no' is not supported by the stylesheets that generate Eclipse Help. - Ignored by the stylesheets that generate Web Help and EPUB.
number-toc-entries	Allowed values are: 'yes' and 'no'. Default value: 'yes' for Web Help, 'no' for the other formats.	If 'yes', number the TOC entries. No effect unless the number parameter is used to specify that topics should be numbered.

Parameters specific to the stylesheets that generate Web Help

Parameter	Value	Description
 <code>wh- - - CSS_VAR_NAME</code>	String. A valid CSS property value. No default.	This kind of parameter may be used to override any of the default values of the CSS variables specified in any of the <code>NNtheme.css</code> template files (all found in <code>ditac_install_dir/whc_template/_wh/</code>). For example, the main <code>NNtheme.css</code> template file: <pre>body { ... --navigation-width: 33%; ... }</pre> The <code>wh- - -navigation-width</code> CSS variable is used as follows in <code>NNcommon.css</code>, another CSS template file: <pre>#wh-navigation { ... width: var(--navigation-width); }</pre>

Parameter	Value	Description
		<pre>... }</pre> Therefore parameter <code>wh---navigation-width</code> may be used to give the navigation side of the generated Web Help a different initial width. Example: <code>-p wh---navigation-width "25%"</code>. More examples in "XMLmind Web Help Compiler Manual, Getting started".
★wh-collapse-toc	Allowed values are: 'yes' and 'no'. Default value: 'no'.	Specifies whether the TOC should be initially collapsed.
★wh-favicon	Filename or absolute URI of an image file. A relative filename is relative to the current working directory.	Specifies the <i>favicon</i> which is to be added to each page of the Web Help. A <i>favicon</i> is a small image displayed next to the page title in the browser tab. This file is copied to <code>output_directory/_wh/user/</code>.
★wh-index-numbers	Allowed values are: 'yes' and 'no'. Default value: 'no'.	Specifies whether words looking like numbers are to be indexed. Examples of such number-like words: 3.14, 3, 14, 3times4equals12, +1, -1.0, 3px, 1, 2cm, 100%, 1.0E+6, 1,000.00\$.
★wh-inherit-font-and-colors	Allowed values are: 'yes' and 'no'. Default value: 'yes'.	When <code>wh-inherit-font-and-colors</code> is set to 'no', the navigation pane of the generated Web Help uses fonts and colors of its own, which will generally differ from those used for the content of the Web Help. Setting <code>wh-inherit-font-and-colors</code> to 'yes' lets you use for the navigation pane the same fonts and colors as those used for the content of the Web Help. So basically this parameter is a shorthand for: <pre>-p wh---navigation-font-family inherit- -p wh---navigation-font-size inherit- -p wh---navigation-color inherit- -p wh---navigation-background-color inherit</pre> See above wh---CSS_VAR_NAME parameters.
★wh-jquery	Relative or absolute URI. A relative URI is relative to the URI of a page of the Web Help. Default value: absolute URI of the correspond-	Specifies the location of the JavaScript file containing jQuery. Example: <pre>https://code.jquery.com/ jquery-3.7.1.slim.min.js</pre>

Parameter	Value	Description
	ing file found on the Google CDN.	Specifying an "https:" URL is recommended when the generated Web Help is stored on an HTTPS server.
★wh-local-jquery	Allowed values are: 'yes' and 'no'. Default value: 'no'.	Specifies whether all jQuery files should be copied to <code>_wh/jquery/</code> , where <code>_wh/</code> is the directory containing the other Web Help files. By default, the jQuery files are accessed from the Web (typically from a CDN). Note that this parameter is applied <i>after</i> jQuery has been possibly customized using parameter <code>wh-jquery</code> . For example, <code>"-p wh-jquery https://code.jquery.com/jquery-3.7.0.js"</code> copies a file downloaded from <code>https://code.jquery.com/</code> to <code>_wh/jquery/</code> .
★wh-layout	The name of a layout. Default value: 'classic'.	Selects a layout for the generated Web Help. For now, only 3 layouts are supported: classic, simple and corporate.
★wh-responsive-ui	Allowed values are: 'yes' and 'no'. Default value: 'yes'.	Specifies whether the generated Web Help should be “responsive”, that is, whether it should adapt its layout to the size of the screen.
★wh-ui-language	"browser" or "document" or a language code conforming RFC 3066. Examples: de, fr-CA. Default value: 'browser'.	Specifies which language should be used for the messages (tab labels, button tool tips, etc) of the generated Web Help. Default value "browser" means that this language is the one used by the Web browser for its own messages. This language may often be specified in the user preferences of the Web browser. Value "document" means that the language of the document should be used. A language code such as en, en-US, es, es-AR, etc, may be used to explicitly specify which language should be used.
★wh-use-stemming	Allowed values are: 'yes' and 'no'. Default value: 'yes'.	Specifies whether <i>stemming</i> ⁽⁶⁾ should be used to implement the search facility. By default, stemming is used whenever possible, that is, 1. when the main language of the document can be determined; 2. when this main language is one of: Danish, Dutch, English, Finnish, French, German,

⁽⁶⁾In linguistic morphology and information retrieval, stemming is the process of reducing inflected (or sometimes derived) words to their word stem, base or root form—generally a written word form.

Parameter	Value	Description
		Hungarian, Italian, Norwegian, Portuguese, Russian, Spanish, Swedish, Romanian, Turkish. The main language of the document is specified by the <code>@xml:lang</code> attribute found on the root element of DITA map being converted; otherwise using the -lang command-line option; otherwise, it is assumed to be "en".
★wh-user-css	Filename or absolute URI of a CSS file. A relative filename is relative to the current working directory.	Specifies the user's CSS stylesheet which is to be added to each page of the Web Help. This file is copied to <i>output_directory/_wh/user/</i>. Sample user's CSS wh_resources/header_footer.css as used in the following example: <pre>-p wh-user-header~ wh_resources/header.html -p wh-user-footer~ wh_resources/footer.html -p wh-user-css~ wh_resources/header_footer.css -p wh-user-resources~ wh_resources/header_footer_files</pre>
★wh-user-footer	Filename or absolute URI of an XHTML file. A relative filename is relative to the current working directory.	Specifies the user's footer which is to be added to each page of the Web Help. The content of the <code><body></code> element of <code>wh-user-footer</code> is inserted as is in the <code><div id="wh-footer"></code> found in each page of the Web Help. Same remark as for parameter <code>wh-user-header</code> about the resources referenced by a user's footer. Sample user's footer wh_resources/footer.html as used in the following example: <pre>-p wh-user-header~ wh_resources/header.html -p wh-user-footer~ wh_resources/footer.html -p wh-user-css~ wh_resources/header_footer.css -p wh-user-resources~ wh_resources/header_footer_files</pre> More examples in "XMLmind Web Help Compiler Manual, Getting started".
★wh-user-header	Filename or absolute URI of an XHTML file.	Specifies the user's header which is to be added to each page of the Web Help.

Parameter	Value	Description
	A relative filename is relative to the current working directory.	The content of the <body> element of wh-user-header is inserted as is in the <div id="wh-header"> found in each page of the Web Help. If a user's header references resources (e.g. image files), then these resources must either be referenced using absolute URLs or these resources must be found in a user's resource directory and parameter wh-user-resources must be specified. Example: - The user's resource directory is called header_footer_files/ and contains header_footer_files/200x100.png. ditac is passed parameters: -p wh-user-resources PATH_TO/header_footer_files and -p wh-user-header-PATH_TO/header.html. - header.html looks like this: <pre><html> ... <body> </body> </html></pre> Notice the path used to reference logo200x100.png. Sample user's header wh_resources/header.html as used in the following example: <pre>-p wh-user-header~ wh_resources/header.html -p wh-user-footer~ wh_resources/footer.html -p wh-user-css~ wh_resources/header_footer.css -p wh-user-resources~ wh_resources/header_footer_files</pre> More examples in "XMLmind Web Help Compiler Manual, Getting started".
★wh-user-resources	Filename or absolute "file:" URI of a directory. URI schemes other than "file" (e.g.	Specifies a user's resource directory which is to be recursively copied to <i>output_directory/_wh/user/</i> .

Parameter	Value	Description
	"http") are not supported for this parameter. A relative filename is relative to the current working directory.	This directory typically contains image files referenced by the user's header, footer or CSS stylesheet. Sample user's resource directory <code>wh_resources/header_footer_files/</code> as used in the following example: <pre>-p wh-user-header~ wh_resources/header.html -p wh-user-footer~ wh_resources/footer.html -p wh-user-css~ wh_resources/header_footer.css -p wh-user-resources~ wh_resources/header_footer_files</pre> More examples in "<i>XMLmind Web Help Compiler Manual, Getting started</i>".
whc-index-basename	URL basename. Default value: 'whc_index.xml'.	Basename of the Index XML input file of XMLmind Web Help Compiler. In principle, there is no need for an end-user to specify this parameter.
whc-toc-basename	URL basename. Default value: 'whc_toc.xml'.	Basename of the TOC XML input file of XMLmind Web Help Compiler. In principle, there is no need for an end-user to specify this parameter.

Parameters specific to the stylesheets that generate HTML Help

In principle, there is no need for an end-user to specify any of the following parameters.

Parameter	Value	Description
 chmBasename	URL basename. Default value: 'help.chm'.	Basename of the compiled HTML Help file.
hhc-basename	URL basename. Default value: 'toc.hhc'.	Basename of the HTML Help contents file.
hhp-template	URL basename. Default value: 'template.hhp' resolved against the directory which contains the XSLT stylesheets.	URL of the file containing the template of the HTML Help project file. This plain text file encoded in UTF-8 contains variables such as <code>%compiledFile%</code> , <code>%contentsFile%</code> , <code>%default-Topic%</code> , etc, which are substituted with their values.
 hhpBasename	URL basename.	Basename of the HTML Help project file.

Parameter	Value	Description
	Default value: 'project.hhp'.	
hhx-basename	URL basename. Default value: 'index.hhx'.	Basename of the HTML Help index file.

Parameters specific to the stylesheets that generate Eclipse Help

Parameter	Value	Description
plugin-id	String No default value.	An ID uniquely identifying the plug-in, typically a Java-like fully qualified name. Example: 'com.acme.widget.userguide'.  Important The subdirectory of plug-ins/ containing the plug-in must have the same base-name as the value of parameter plugin-id.
plugin-index-base-name	URL basename. Default value: 'index.xml'.	Basename of the index file.
plugin-name	String No default value.	The name of the plug-in, typically the title of the document. Example: 'ACME Widget User&a-pos;s Guide'.
plugin-provider	String No default value.	The author, company or organization which has contributed the plug-in. Example: 'ACME Corp. '.
plugin-toc-base-name	URL basename. Default value: 'toc.xml'.	Basename of the table of contents file.
plugin-version	String Default value: '1.0.0'.	The version of the plug-in.

Parameters specific to the stylesheets that generate EPUB

Parameter	Value	Description
cover-image	URI. If the URI is relative, it is relative to the	Specifies an image file which is to be used as the cover page of the EPUB file. This image must be

Parameter	Value	Description
	current working directory of the user. No default value.	a PNG or JPEG image. Its size must not exceed 1000x1000 pixels. In theory, EPUB 3 also accepts SVG 1.1 cover images.
epub-identifier	String Default value: dynamically generated UUID URN.	A globally unique identifier for the generated EPUB document (typically the permanent URL of the EPUB document).
epub2-compatible	Allowed values are: 'yes' and 'no'. Default value: 'yes'.	Only applies to EPUB 3. By default, the EPUB 3 files generated by ditac are made compatible with EPUB 2 readers. Specify 'no' if you don't need this compatibility.

Parameters specific to the stylesheets that generate XSL-FO

The XSL-FO file generated by the XSLT stylesheets is converted to PDF, PostScript®, RTF, WordprocessingML, Office Open XML (.docx), OpenOffice/LibreOffice (.odt) by the means of XSL-FO processors such as [Apache FOP](#), [RenderX XEP](#), [Antenna House XSL Formatter](#) or [XMLmind XSL-FO Converter](#).



Tip

Inserting a `<?pagebreak?>` processing-instruction in the topic source between paragraphs, notes, tables, lists, etc, may be used to force a page break when generating any of the output formats which uses XSL-FO as an intermediate format (PDF, RTF, DOCX, etc).

Parameter	Value	Description
base-font-size	Default value: '10pt'.	The size of the ``main font" of the document. All the other font sizes are computed relatively to this font size
body-bottom-margin	Length. Default value: '0.5in'.	See Figure 4-1 below.
body-font-family	A string containing one or more font families separated by commas. Default value: 'serif'.	Specifies the family of the font used for the text of all elements except topic titles.
body-start-indent	Length. Default value: '2pc'.	Applies only to <i>alternate XSLT stylesheet ditac_install_dir/xsl/fo/fo_indent.xsl</i> . This stylesheet:

Parameter	Value	Description
		- Indents all blocks but topic and section titles by the value of XSLT stylesheet parameter <i>body-start-indent</i>. By default <i>body-start-indent</i> is 2pc. - Adds more vertical space after topic and section titles. - Only part, appendices, chapter and appendix titles are underlined. This stylesheet is invoked by passing option <code>-t ditac-xsl:fo/fo_indent.xsl</code> to ditac. Example of its output: manual-fop.pdf.
body-top-margin	Length. Default value: '0.5in'.	See Figure 4-1 below.
choice-bullets	A string containing one or more single characters separated by whitespace. Default value: '•' (BULLET).	Specify which bullet character to use for a <choice> element. Additional characters are used for nested <choice> elements. Changing the value of this parameter may imply changing the font-family attribute of the attribute-set choice-label.
equation-block-equation-width	Length. Default value: '90%'.	In a numbered <equation-block> element, this parameter specifies the width of the column containing the equation.
equation-block-number-width	Length. Default value: '10%'.	In a numbered <equation-block> element, this parameter specifies the width of the column containing the <equation-number> element.
external-href-after	String. Default value: ']'.	Appended after the external URL referenced by an <xref> or <link> element. Ignored unless show-external-links='yes'.
external-href-before	String. Default value: '['.	Separates the text of an <xref> or <link> element from its referenced external URL. Ignored unless show-external-links='yes'.
 foProcessor	String. Examples: 'FOP', 'XEP', 'AHF', 'XFC'. Default value: ''.	The name of the XSL-FO processor used to convert the XSL-FO file generated by the XSLT stylesheets to the target output format.
footer-center	String.	Specifies the contents of the central part of a page footer. See Specifying a header or a footer . Supports a conditional specification . Default value: <pre>two-sides even:: {{chapter-title}};; two-sides part chapter appendices appendix odd::-</pre>

Parameter	Value	Description
		<pre> {{section1-title}};; one-side:: {{chapter-title}} </pre>
footer-center-width	String representing an integer larger than or equal to 1. Default value: '6'.	Specifies the proportional width of the central part of a page footer. See Specifying a header or a footer . Supports a conditional specification .
footer-height	Length. Default value: '0.4in'.	See Figure 4-1 below.
footer-left	String.	Specifies the contents of the left part of a page footer. See Specifying a header or a footer . Supports a conditional specification . Default value: <pre> two-sides even:: {{page-number}} </pre>
footer-left-width	String representing an integer larger than or equal to 1. Default value: '2'.	Specifies the proportional width of the left part of a page footer. See Specifying a header or a footer . Supports a conditional specification .
footer-right	String.	Specifies the contents of the right part of a page footer. See Specifying a header or a footer . Supports a conditional specification . Default value: <pre> two-sides first odd:: {{page-number}};; one-side:: {{page-number}} </pre>
footer-right-width	String representing an integer larger than or equal to 1. Default value: '2'.	Specifies the proportional width of the right part of a page footer. See Specifying a header or a footer . Supports a conditional specification .
footer-separator	Allowed values are: 'yes' and 'no'. Default value: 'yes'.	Specifies whether an horizontal rule should be drawn above the page footer.
header-center	String. Default value: '{{document-title}}'.	Specifies the contents of the central part of a page header. See Specifying a header or a footer . Supports a conditional specification .

Parameter	Value	Description
header-center-width	String representing an integer larger than or equal to 1. Default value: '6'.	Specifies the proportional width of the central part of a page header. See Specifying a header or a footer . Supports a conditional specification .
header-height	Length. Default value: '0.4in'.	See Figure 4-1 below.
header-left	String. Default value: ''.	Specifies the contents of the left part of a page header. See Specifying a header or a footer . Supports a conditional specification .
header-left-width	String representing an integer larger than or equal to 1. Default value: '2'.	Specifies the proportional width of the left part of a page header. See Specifying a header or a footer . Supports a conditional specification .
header-right	String. Default value: ''.	Specifies the contents of the right part of a page header. See Specifying a header or a footer . Supports a conditional specification .
header-right-width	String representing an integer larger than or equal to 1. Default value: '2'.	Specifies the proportional width of the right part of a page header. See Specifying a header or a footer . Supports a conditional specification .
header-separator	Allowed values are: 'yes' and 'no'. Default value: 'yes'.	Specifies whether an horizontal rule should be drawn below the page header.
hyphenate	Allowed values are: 'yes' and 'no'. Default value: 'no'.	Specifies whether words may be hyphenated.
index-column-count	Positive integer. Default value: '2'.	The number of columns of index pages.
index-column-gap	Length. Default value: '2em'.	The distance which separates columns in index pages.
justified	Allowed values are: 'yes' and 'no'.	Specifies whether text (e.g. in paragraphs) should be justified (that is, flush left and right) or just left aligned (that is, flush left and ragged right).

Parameter	Value	Description
	Default value: 'no'.	
link-bullet	A string containing a single character. Default value: '•' (BULLET).	Specify which character is inserted before the text of a <link> element. Changing the value of this parameter may imply changing the font-family attribute of the attribute-set link-bullet.
menucas-cade-separator	A string containing a single character. Default value: '→' (RIGHTWARDS ARROW).	Specify which character is used to separate the child elements of a <menucascade> element. Changing the value of this parameter may imply changing the font-family attribute of the attribute-set menucas-cade-separator.
note-icon-height	Length. A length may have a unit. Default is px. Default value: '32'. '7mm' for the XSLT stylesheets that generate XSL-FO.	The height of a note icon.
note-icon-suffix	Default value: ' .png'.	The suffix of a note icon. The root name of a note icon should be identical to the value of the @type attribute it represents. For example, if note-icon-suffix=' .svg', the default resources directory is expected to contain note.svg, important.svg, caution.svg, etc. In principle, there is no need for an end-user to specify any of the note-icon-suffix, note-icon-width or note-icon-height parameters.
note-icon-width	Length. A length may have a unit. Default is px. Default value: '32'. '7mm' for the XSLT stylesheets that generate XSL-FO.	The width of a note icon.
page-bottom-margin	Length. Default value: '0.5in'.	See Figure 4-1 below.
page-height	Length. Example: '297mm'.	The height of the printed page.


Parameter	Value	Description
	Default value: depends on pa- per-type.	
page-in- ner-margin	Length. Default value: if parameter two- sided is speci- fied as 'yes' then '1.25in' other- wise '1in'.	See Figure 4-1 below.
page-orienta- tion	Allowed values are: 'portrait' and 'land- scape'. Default value: 'portrait'.	The orientation of the printed page.
page-out- er-margin	Length. Default value: if parameter two- sided is speci- fied as 'yes' then '0.75in' other- wise '1in'.	See Figure 4-1 below.
page-ref-after	String. Default value: ' '.	Appended after the page number pointed to by an <xref> or <link> element. Ignored unless show-xref-page='yes' or show-link-page='yes'. When both page-ref-after and page-ref-before are specified as the empty string, in fact, this specifies that the generated string must be the localized equivalent of "on page".
page-ref-be- fore	String. Default value: ' '.	Separates the text of an <xref> or <link> element from the page number it points to. Ignored unless show-xref-page='yes' or show-link-page='yes'.
page-top-mar- gin	Length. Default value: '0.5in'.	See Figure 4-1 below.
page-width	Length. Example: '8.5in'. Default value: depends on pa- per-type.	The width of the printed page.
paper - type	Allowed val- ues are: 'Let -	A convenient way to specify the size of the printed page.

Parameter	Value	Description
	ter', 'Legal', 'Ledger', 'Tabloid', 'A0', 'A1', 'A2', 'A3', 'A4', 'A5', 'A6', 'A7', 'A8', 'A9', 'A10', 'B0', 'B1', 'B2', 'B3', 'B4', 'B5', 'B6', 'B7', 'B8', 'B9', 'B10', 'C0', 'C1', 'C2', 'C3', 'C4', 'C5', 'C6', 'C7', 'C8', 'C9', 'C10' (case-insensitive). Default value: 'A4'.	It is also possible to specify a custom paper type by ignoring the paper-type parameter and directly specifying the page-width and page-height parameters.
pdf-outline	Allowed values are: 'yes' and 'no'. Default value: 'no'.	Specifies whether PDF bookmarks should be generated. Supported by the 'XEP', 'FOP' and 'AHF' XSL-FO processors. Not relevant, and thus ignored by 'XFC'.
show-external-links	Allowed values are: 'yes' and 'no'. Default value: 'no'.	Specifies whether the <i>external URL</i> referenced by an <xref> or <link> element should be displayed right after the text contained by this element. Example: show-external-links='yes' causes <xref href="http://www.oasis-open.org/">Oasis</xref> to be rendered as follows: Oasis [http://www.oasis-open.org/].
show-imagemap-links	Allowed values are: 'yes' and 'no'. Default value: 'yes'.	Specifies whether a numbered list should be generated for an <imagemap> element, with one list item per <area> element. A list item contains the link specified by the <area> element. No list items are generated for “dead areas” (<area> elements specifying no link at all).
show-link-page	Allowed values are: 'yes' and 'no'. Default value: 'no'.	Same as show-xref-page but for <link> elements.
show-xref-page	Allowed values are: 'yes' and 'no'.	Specifies whether the page number corresponding to the <i>internal link target</i> referenced by an <xref> element should be displayed right after the text contained by this element.

Parameter	Value	Description
	Default value: 'no'.	Example: <code>show-xref-page='yes'</code> causes <code><xref href="introduction.dita">Introduction</xref></code> to be rendered as follows: Introduction [3]. See also parameters xref-auto-text , page-ref-before , page-ref-after .
title-color	A string representing a color. Default value: 'black'.	Specifies the color used for the text of topic (of any kind) titles.
title-font-family	A string containing one or more font families separated by commas. Default value: 'sans-serif'.	Specifies the family of the font used for the text of topic (of any kind) titles.
two-sided	Allowed values are: 'yes' and 'no'. Default value: 'no'.	Specifies whether the document should be printed double sided.
ul-li-bullets	A string containing one or more single characters separated by whitespace. Default value: '•' (BULLET, EN DASH).	Specify which bullet character to use for an <code>/</code> element. Additional characters are used for nested <code></code> elements. For example, if <code>ul-li-bullets="* - +"</code> , <code>"*"</code> will be used for <code>/</code> elements, <code>"-"</code> will be used for <code>/</code> elements contained in a <code>/</code> element and <code>"+"</code> will be used for <code>/</code> elements nested in two <code>/</code> elements. Changing the value of this parameter may imply changing the <code>font-family</code> attribute of the attribute-set <code>ul-li-label</code> .
un-ordered-step-bullets	A string containing one or more single characters separated by whitespace. Default value: '•' (BULLET, EN DASH).	Specify which bullet character to use for a <code><steps-unordered>/<step></code> element. Additional characters are used for nested <code><steps-unordered>/<step></code> elements. Changing the value of this parameter may imply changing the <code>font-family</code> attribute of the attribute-set <code>un-ordered-step-label</code> .
watermark	Allowed values are one or more of 'blank', 'title', 'toc', 'booklist', 'frontmatter', 'body', 'back-	Specifies which pages in the output document are to be given a watermark. By default, all pages are given a watermark. If for example, parameter <code>watermark</code> is set to <code>'frontmatter body backmatter'</code> , then only the pages which are part of the front matter, body and back matter of the output document are giv-

Parameter	Value	Description
	matter', 'index', 'all' separated by white-space. Default value: 'all'.	en a watermark. The title page, TOC pages, etc, are not given a watermark. No effect unless parameter <code>watermark-image</code> is specified.
<code>xfc-render-as-table</code>	A string containing zero or more DITA element names separated by white-space. Default value: 'note'.	Specifies whether XMLmind XSL-FO Converter should render the <code><fo:block>s</code> representing specified DITA elements as <code><fo:table>s</code> . This parameter enables a workaround for a limitation of XMLmind XSL-FO Converter: a <code><fo:block></code> having a border and/or background color and containing several other blocks, lists or tables is very poorly rendered in RTF, WML, DOCX and ODT.

Figure 4-1. Page areas




1. Page headers and footers

Specifying a header or a footer

The header or the footer of a generated PDF, RTF, etc, page has 3 columns.

Figure 4-2. Layout of a header



The width of these columns may be specified using the `header-left-width`, `header-center-width`, `header-right-width` parameters for the header and the `footer-left-width`, `footer-center-width`, `footer-right-width` parameters for the footer.

The width of a column is specified as an integer which is larger than or equal to 1. This value is the *proportional width of the column*. For example, if the left column has a width equal to 2 and the right column has a width equal to 4, this simply means that the right column is twice ($4/2 = 2$) as wide as the left column.

The contents of these columns may be specified using the `header-left`, `header-center`, `header-right` parameters for the header and the `footer-left`, `footer-center`, `footer-right` parameters for the footer.

When `header-left`, `header-center`, `header-right` are all specified as the empty string, no header is generated. When `footer-left`, `footer-center`, `footer-right` are all specified as the empty string, no footer is generated.

The content of a column is basically a mix of text and variables. Example: "Page `{{page-number}}` of `{{page-count}}`".

Supported variables are:

`{{document-title}}`

The title of the document.

`{{document-date}}`

The publication date of the document.

The value of the variable comes from the last created or revised element found in the `topicmeta/critdates` or `bookmeta/critdates` element of the map. More precisely, it comes the value of attribute `golive`, `modified` or `date`, considered in that order. The value of this attribute must be something like `YYYY-MM-DD`, because it is parsed and then formatted according to the `xml:lang` of the map. For example, if `golive="2014-02-23"`, with `xml:lang="en"`, it gives: "February 02, 2014" and with `xml:lang="fr"`, it gives: "02 Février 2014". If the map has no `critdates` element, then the current date is used. If the value of attribute `golive`, `modified` or `date` is not specified as `YYYY-MM-DD`, then this value is used as is.

`{{chapter-title}}`

The title of the current part, chapter, appendices or appendix. Empty if the map being converted is not a bookmap.

{{section1-title}}

The title of the current part, chapter, appendices or appendix or *section 1*. A section 1 is specified by a non-typed topicref (that is, not a part, chapter, preface, appendix, dedication, etc) which is a direct child of a map or bookmap.

{{topic-title}}

The title of the current topic. All topics are guaranteed to have a corresponding **{{topic-title}}**. Even automatically generated topics such as toc or indexlist have a corresponding **{{topic-title}}**⁽⁷⁾.

**Restriction**

If you use [XMLmind XSL-FO Converter](#) to convert your DITA document to RTF, WML, DOCX or ODT, then **{{section1-title}}** and **{{topic-title}}** won't work. (**{{chapter-title}}** works fine though.) The reason of this limitation is that, unlike other XSL-FO processors, XMLmind XSL-FO Converter does not implement `<fo:marker>` and `<fo:retrieve-marker>`.

{{page-number}}

Current page number within the current document division (front matter, body matter or back matter).

{{page-count}}

Total number of pages of the current document division (front matter, body matter or back matter).

{{break}}

A line break.

{{image(URI)}}

An image having specified URI. A relative URI is resolved against the current working directory. Example: `"{{image(artwork/logo.svg) }}"`.

{{page-sequence}}

Not for production use. Inserts in the header/footer the name of the current page sequence. This allows to learn which name to use in a *conditional header or footer*. See [below](#).

Conditional headers and footers

The default value of header-center is `'{{document-title}}'`. This means that each page of the generated PDF, RTF, etc, file will have the document title centered on its top. But what if you want the pages containing the Table of Contents have a **"Contents"** header? Is there a way to specify: use **"Contents"** for the pages containing the Table of Contents and use the title of the document for any other page?

This is done by specifying the following conditional value for parameter `header-center`: `'toc:: Contents;; {{document-title}}'`.

A conditional value may contain one or more cases separated by `;;`. Each case is tested against the page being generated. The first case which matches the page being generated is the one which is selected.

*conditional_value --> case [";;" case]**

⁽⁷⁾The **{{topic-title}}** of a toc is **"Table of Contents"**, properly localized. The **{{topic-title}}** of an indexlist is **"Index"**, properly localized.

```
case --> [ condition "::" ]* value
```

```
condition --> [ test_page_sequence ]?
               & [ S test_page_layout ]?
               & [ S test_page_side ]?
```

Let's suppose you also want the the pages containing the Index have a "**Index**" header. Specifying 'toc:: Contents;; {{document-title}};; indexlist:: Index' won't work as expected because the second case (having no condition at all) matches any page, including the Index pages. You need to specify: 'toc:: Contents;; indexlist:: Index;; {{document-title}}'.

Let's remember that variable `{{topic-title}}` is substituted with the title of the current topic, including automatically generated topics such toc and indexlist.

Therefore our conditional value is better expressed as: 'toc:: indexlist:: {{topic-title}};; {{document-title}}'. Notice how a case may have several conditions. Suffice for any of these conditions to match the page being generated for the case to be selected.

Even better, specify 'toc||indexlist:: {{topic-title}};; {{document-title}}'. String "||" may be used to separate alternative values to be tested against the page being generated.

```
test_page_sequence --> page_sequence [ "||" page_sequence ]*

page_sequence --> "abbrevlist" | "amendments" | "appendices" | "appendix"
                  | "backmattersection" | "bibliolist" | "bookabstract" | "booklist"
                  | "chapter" | "colophon" | "dedication" | "draftintro"
                  | "figurelist" | "glossarylist" | "indexlist" | "notices"
                  | "part" | "preface" | "section1" | "tablelist"
                  | "toc" | "trademarklist"
```



Tip

It's not difficult to guess that the name of the page sequence corresponding to the Table of Contents is toc and that the name of the page sequence corresponding to the Index is indexlist. However the simplest way to learn what is the name of the page sequence being generated is to reference variable `{{page-sequence}}` in the specification of a header or a footer.

Now let's suppose that we want to suppress the document title on the first page of a part, chapter or appendix. This is specified as follows: 'first part||chapter||appendix:: ;; toc||indexlist:: {{topic-title}};; {{document-title}}'.

For now, we have only described a condition about the page sequence being generated: TOC, Index, etc. In fact, a condition may test up to 3 facets of the page being generated:

- The page sequence to which belongs the page being generated.
- Whether the page being generated is part of a one-sided or a two-sided document.
- Whether the page being generated is the first page of its sequence. When the the page being generated is *not* the first page of its sequence, if the page being generated has an odd or an even page number.

```
test_page_layout --> page_layout [ "||" page_layout ]*
```

```
page_layout --> "two-sides" | "one-side"
```

```
test_page_side --> page_side [ "|" page_side ]*
```

```
page_side --> "first" | "odd" | "even"
```



Remember

When the document has one side, the only possible page side is odd. The other values, first and even, are not supported. For example, something like 'one-side chapter||appendix even:: {{chapter-title}};' cannot generate any text.

The order of the tests is not significant. For example, 'first part||chapter||appendix' is equivalent to 'part||chapter||appendix first'.

Therefore 'first part||chapter||appendix:: ;; toc||indexlist:: {{topic-title}};; {{document-title}}' reads as follows:

1. Use the empty string for the first page of a part, chapter or appendix.
2. Use the topic title for the pages containing the Table of Contents. This title is "**Table of Contents**", but localized according to the main language of the DITA document being converted.
3. Use the topic title for the pages containing the Index. This title is "**Index**", but localized according to the main language of the DITA document being converted.
4. For any other page, use the title of the DITA document.



Note

Everything explained in this section applies not only to the contents of a column of a header or footer, but also to the proportional width of a column of a header or footer. Example: - p footer-right-width "first||odd:: 4;; even:: 1".

Chapter 5. Controlling the numbering of ordered lists

This chapter explains how you can control the numbering of ordered lists by the means of one or more directives specified in the `@outputclass` attribute of the `<ol>` element.

By default, the numbering of nested ordered lists automatically alternates between the "1." and "a." formats. If you want more control on the numbering of ordered lists, then you'll have to specify one or more of the following directives in the `@outputclass` attribute of the `<ol>` element.

lower-alpha

upper-alpha

lower-roman

upper-roman

decimal

Specifies the style of numbering.

start(*positive_integer*)

Numbering begins at specified *positive_integer*.

continue

Numbering begins where the preceding ordered list left off.

inheritnum

Numbering inherits from outer-level ordered lists. For example, using this feature (e.g. `<ol outputclass="upper-alpha inheritnum">`), the items of a list nested at level 2 are labelled "1.A.", "1.B.", "1.C.", etc.



Restriction

- When using [XMLmind XSL-FO Converter v6.0+^{\(8\)}](#) to generate RTF, WML, DOCX or ODT, directive `inheritnum` is supported but with minor limitations. For example, when both `start(positive_integer)` and `inheritnum` are specified, `inheritnum` is not honored.
- Directive `inheritnum` is not honored when generating Java Help and HTML Help.

Example: `<ol outputclass="upper-roman start(10)">` specifies an ordered list which starts with an "X.".

Note that it is still possible to specify any class name you want in the `@outputclass` attribute of the `<ol>` element. Example: `<ol outputclass="continue fancy-list">`.

⁽⁸⁾v6.1+ strongly recommended.

Chapter 6. Giving a background color to table cells

This chapter explains how you can give a background color to table cells by adding a `bgcolor(color)` directive to the `@outputclass` attribute of most table elements.

It's possible to give a background color to table cells by adding a `bgcolor(color)` directive, where *color* is any CSS color value, to the `@outputclass` attribute of the following elements:

Inside a `<simpletable>` element

`<simpletable>`, `<sthead>`, `<strow>`, `<stentry>`.

Inside a `<table>` element

`<tgroup>`, `<thead>`, `<tbody>`, `<row>`, `<entry>`.

Example:

```
<table>
  <tgroup cols="2" outputclass="bgcolor(#F0FFFF)">
    <tbody>
      <row>
        <entry>C1,1</entry>
        <entry>C1,2</entry>
      </row>
      <row outputclass="bgcolor(#FFFFF0)">
        <entry>C2,1</entry>
        <entry>C2,2</entry>
      </row>
    </tbody>
  </tgroup>
</table>
```

Note that it is still possible to specify any class name you want in the `@outputclass` attribute of a table element. Example: `<simpletable outputclass="bgcolor(#FFFFF0) fancy-table">`.

Chapter 7. Fancy code blocks

This section explains how you can automatically add line numbers, “expand” tab characters and colorize the source code contained in `<pre>`, `<codeblock>` or any other element specializing `<pre>`.

Adding line numbers, “expanding” tab characters and colorizing the source code contained in `<pre>`, `<codeblock>` or any other element specializing `<pre>` is done by adding one or more of the following classes to the `@outputclass` attribute of this element:

line-numbers

line-numbers-*N* (where *N* is an integer > 0)

show-line-numbers

Give a number to the lines contained in the `<pre>` element.

By default, first line number is 1. This first line may be specified using the second form of the `line-numbers` class, for example, `line-numbers-100` specifies that lines are to be numbered and that first line number is 100.

`show-line-numbers`, an alias for `line-numbers-1`, is also accepted for [compatibility with the DITA-OT](#).

language-*L* (where *L* is language name)

Colorize the source code contained in the `<pre>` element. *L*, a “programming language” such as `c`, `java`, `css`, `xml`, specifies how the source code should be colorized.

More information about this feature, commonly called *syntax highlighting*, in [next section](#).

tab-width-*W* (where *W* is an integer >= 0)

normalize-space

Specifies whether tab characters should be expanded to a number of space characters. *W* is the maximum number of space characters for an expanded tab character, hence this value specifies the location of “tab stops”. Examples: `tab-width-4` means: expand tabs to up to 4 space characters; `tab-width-0` means: do not replace tabs by space characters.

In addition to replacing tab characters by a number of space characters, `tab-width-W` (where *W* > 0) also removes the space characters which are common to the beginning of all text lines. That is, it removes the superfluous “indentation” in the `<pre>` element, if any. See [example below](#).

Moreover `tab-width-W` (where *W* > 0) also removes the (useless) space characters found just before newline characters.

`normalize-space`, an alias for `tab-width-8`, is also accepted for [compatibility with the DITA-OT](#).



Remember

When the `<outputclass>` attribute of any element specializing `<pre>` contains class `line-numbers/line-numbers-N` and/or class `language-L`, then class `tab-width-8` is implicitly specified too, that is, whitespace normalization is automatically performed. If this is not what you want, please explicitly add class `tab-width-0` to `@outputclass`.

Example: a simple C program featuring line numbering and syntax highlighting

In the following C program, lines are indented using tab characters.

```

1 <pre outputclass="language-c line-numbers tab-width-4">/* Hello World */
2 #include <stdio.h>;
3
4 int main()
5 {
6     printf("Hello World\n");
7     return 0;
8 }</pre>

```

is rendered as:

```

1 /* Hello World */
2 #include <stdio.h>
3
4 int main()
5 {
6     printf("Hello World\n");
7     return 0;
8 }

```

Example: superfluous indentation is removed by tab-width-*N* (where *N* > 0)

Attribute @outputclass implicitly also contains tab-width-8. First line " /tmp/" starts with 4 space characters.

```

1 <pre outputclass="line-numbers"> /tmp/
2     /usr/
3         bin/
4         lib/
5         <b>local/</b>
6             <b>bin/</b>
7             <b>lib/</b>
8             <b>src/</b>
9         src/
10    /var/
11 </pre>

```

is rendered as:

```

1 /tmp/
2 /usr/
3     bin/
4     lib/
5     local/
6         bin/
7         lib/
8         src/
9     src/
10 /var/
11

```

1. Syntax highlighting

This section explains how you can automatically colorize the source code contained in `<pre>`, `<codeblock>` or any other element specializing `<pre>`.

You can automatically colorize the source code contained in `<pre>`, `<codeblock>` or any other element specializing `<pre>`. This feature, commonly called *syntax highlighting*, has been implemented using an open source software component called "[XSLT syntax highlighting](#)".

If you want to turn on syntax highlighting in a DITA document, suffice to add attribute `@outputclass` to a `<pre>`, `<codeblock>` or any other element specializing `<pre>`. The value of attribute `@outputclass` must be any of: `language-bourne` (or `-shell` or `-sh`), `language-c`, `language-cmake` (or `-make` or `-makefile`), `language-cpp`, `language-csharp`, `language-css21` (or `-css`), `language-delphi`, `language-ini`, `language-java`, `language-javascript`, `language-lua`, `language-m2` (Modula 2), `language-perl`, `language-php`, `language-python`, `language-ruby`, `language-sql1999`, `language-sql2003`, `language-sql92` (or `-sql`), `language-tcl`, `language-upc` (Unified Parallel C), `language-html`, `language-xml`.

If you want to customize syntax highlighting for an HTML-based output format (XHTML, EPUB, etc), then redefine any of the following CSS styles:

- `.hl-keyword` (keywords of a programming language),
- `.hl-string` (string literal),
- `.hl-number` (number literal),
- `.hl-comment` (any type of comment),
- `.hl-doccomment` (comments used as documentation, i.e. javadoc, or xmldoc),
- `.hl-directive` (preprocessor directive or in XML, a processing-instruction),
- `.hl-annotation` (annotations or "attributes" as they are called in .NET),
- `.hl-tag` (XML tag, i.e. element name),
- `.hl-attribute` (XML attribute name),
- `.hl-value` (XML attribute value),
- `.hl-doctype` (`<!DOCTYPE>` and all its content).

Example: customization of the syntax highlighting of a keyword for HTML-based output formats

```
.hl-keyword {
    font-weight: bold;
    color: #602060;
}
```

How to use a custom CSS stylesheet is explained in [Part II, Chapter 9, Section 1](#).

If you want to customize syntax highlighting for an XSL-FO-based output format (PDF, RTF, etc), then redefine any of the following `<attribute-set>`s: `hl-keyword`, `hl-string`, `hl-number`, `hl-comment`, `hl-doccomment`, `hl-directive`, `hl-annotation`, `hl-tag`, `hl-attribute`, `hl-value`, `hl-doctype`.

Example: customization of the syntax highlighting of a keyword for XSL-FO-based output formats

```
<xsl:attribute-set name="hl-keyword" use-attribute-sets="hl-style">
  <xsl:attribute name="font-weight">bold</xsl:attribute>
  <xsl:attribute name="color">#602060</xsl:attribute>
</xsl:attribute-set>
```

How to use a custom XSLT stylesheet generating XSL-FO is explained in [Part II, Chapter 9, Section 2](#).

Chapter 8. Rich media content

This chapter explains how to add SVG, MathML, TeX/LaTeX math, audio, video and Flash animations to your DITA topics and how **dita** processes this rich media content in the case where the output format supports rich media (e.g. XHTML 5, EPUB 3) and also in the case where the output format does not support rich media (e.g. XHTML 1, PDF, RTF).

SVG

It is possible to include SVG graphics in a DITA document either by reference or by inclusion. Use an `<svg-container>/<svgref>` element pointing to an SVG file to include it by reference. Example:



The XML source code corresponding to the above example is:

```
<p><svg-container><svgref href="media/graphic.svg"/></svg-container></p>
```

It's also possible to use an `<image>` element pointing to an SVG file to include it by reference. Example:

```
<p><image href="media/graphic.svg"/></p>
```

Embedding SVG graphics in a DITA document can be achieved using the same `<svg-container>` element. Example:



The XML source code corresponding to the above example is:

```
<p><svg-container>
  <svg:svg height="64.710144" version="1.1"
    viewBox="0 0 104.28986 51.768115" width="130.36232"
    xmlns:svg="http://www.w3.org/2000/svg">
    ...
  </svg:svg>
</svg-container></p>
```

Embedding SVG

- It is still recommended to include SVG graphics by reference using the `<image>` element rather than `<svg-container>/<svgref>`. The `<image>` element has useful attributes (`@width`, `@height`, `@scale`, `@scalefit`) allowing to adjust the dimension of the image. Moreover this elements permits on the fly conversion between image formats.
- It is not recommended to embed SVG elements in a DITA document as this is likely to cause many validation problems.
- An embedded SVG element is kept embedded only when generating the following output formats: XHTML 5, XHTML 5 Web Help, EPUB 3 and all XSL-FO based output formats (PDF,

RTF, DOCX, etc). For any other output format, an embedded SVG element is automatically extracted and replaced by an <image> element pointing to a ".svg" file.

MathML

It is possible to include math in a DITA document either by reference or by inclusion. Use an <mathml>/<mathmlref> element pointing to a MathML file to include it by reference. Example:

$$R_0 = \left| \frac{n_1 - n_2}{n_1 + n_2} \right|^2$$

The XML source code corresponding to the above example is:

```
<p><mathml><mathmlref href="media/math.mml"/></mathml></p>
```

Embedding MathML in a DITA document can be achieved using the same <mathml> element. Example:

$$\begin{cases} \nabla \times \mathbf{E} = -\frac{\partial \mathbf{B}}{\partial t} \\ \nabla \times \mathbf{B} = \mu_0 \mathbf{J} + \mu_0 \epsilon_0 \frac{\partial \mathbf{E}}{\partial t} \end{cases}$$

The XML source code corresponding to the above example is:

```
<p><mathml>
  <m:math display="block"
    xmlns:m="http://www.w3.org/1998/Math/MathML">
    <m:row>
      ...
    </m:row>
  </m:math>
</mathml></p>
```

For clarity, it is recommended to wrap <mathml> into the following equation elements: <equation-in-line>, <equation-block>, <equation-figure>. Example:

Equation 8-1. Reflectance (case of normal incidence)

$$R_0 = \left| \frac{n_1 - n_2}{n_1 + n_2} \right|^2$$

The XML source code corresponding to the above example is:

```
<equation-figure>
  <title>Reflectance (case of normal incidence)</title>
  <mathml>
    <m:math display="block"
      xmlns:m="http://www.w3.org/1998/Math/MathML">
      <m:row>
        ...
      </m:row>
    </m:math>
  </mathml>
</equation-figure>
```

Other example, <equation-block> elements containing a empty <equation-number> (to be automatically filled with an equation number):

$$R_0 = \left| \frac{n_1 - n_2}{n_1 + n_2} \right|^2 \quad (8-1)$$

Note that the counter used to number <equation-figure> elements having a <title> and the counter used to number <equation-block> elements containing an empty <equation-number> are different. Therefore mixing numbered <equation-figure>s and numbered <equation-block>s in the same DITA document may result in a hard to understand equation numbering.

Embedding MathML

- An embedded MathML element is kept embedded only when generating the following output formats: XHTML 5, XHTML 5 Web Help, EPUB 3 and all XSL-FO based output formats (PDF, RTF, DOCX, etc), but only when [Apache FOP](#) or [XMLmind XSL-FO Converter](#) are used as an XSL-FO processor⁽⁹⁾. For any other output format, an embedded MathML element is automatically extracted and replaced by an <image> element pointing to a ".mm1" file.
 - Though a number of web browsers natively support embedded MathML, it's recommended to specify XSLT stylesheet parameter `mathjax` to let [MathJax](#) render embedded MathML found in the generated XHTML 5 and XHTML 5 Web Help files.
 - A ".mm1" file is automatically converted to SVG or PNG by the means of the [JEuclid](#) image converter. Such image converter is found the `ditac-N_N_N-plus-fop.zip` distribution and is automatically registered with ditac.
-

TeX/LaTeX math

Embedding TeX/LaTeX math in a DITA document can be achieved by inserting a <foreign> element having an @outputclass attribute containing "embed-latex"⁽¹⁰⁾ preferably into an <equation-inline>, <equation-block> or <equation-figure> element. Example:

$$\int_0^{\infty} e^{-x} dx \quad (8-2)$$

The XML source code corresponding to the above example is:

```
<equation-block><foreign outputclass="embed-latex"
  >$$\int_0^{\infty} \mathrm{e}^{-x}\mathrm{d}x$$</foreign>
  <equation-number/>
</equation-block>
```

⁽⁹⁾RenderX XEP does not support MathML. [Antenna House Formatter](#) supports MathML as an option.

⁽¹⁰⁾For compatibility with an existing DITA-OT plug-in, one of its test equations being

$$\lim_{x \rightarrow 0} \frac{e^x - 1}{2x} \stackrel{\frac{0}{0}}{=} \lim_{x \rightarrow 0} \frac{e^x}{2} = \frac{1}{2}.$$

**Tip**

TeX/LaTeX math delimiters are optional. However specifying them may be useful as `\[math\]`, `$$math$$` or `\begin{env_name}math\end{env_name}` specify displayed math, while `\(math\)` or `$math$` specify in-line math.

It's also possible to insert an `<image>` element pointing to an ".tex" file into an `<equation-inline>`, `<equation-block>` or `<equation-figure>` element. Example: $\lim_{x \rightarrow \infty} \exp(-x) = 0$.

The XML source code corresponding to the above example is:

```
<p>... Example:
<equation-inline><image href="media/limits.tex"/></equation-inline>.</p>
```

Embedding TeX math

- EmbeddedTeX/LaTeX math is kept embedded only when generating the following output formats: XHTML 5 and XHTML 5 Web Help. For any other output format, EmbeddedTeX/LaTeX math is automatically extracted and replaced by an `<image>` element pointing to a ".tex" file.
- XSLT stylesheet parameter `mathjax` *must be specified* to let **MathJax** render embedded-TeX/LaTeX math found in the generated XHTML 5 and XHTML 5 Web Help files.
- A ".tex" file is automatically converted to SVG or PNG by the means of the **JLaTeXMath** image converter. Such image converter is found in the `ditac-N_N_N-plus-fop.zip` distribution and is automatically registered with ditac.

JLaTeXMath is currently less capable than **MathJax**, yet all the following TeX/LaTeX commands are available:

- macros from *amsmath* and symbols from *amssymb* and *stmaryrd*
- TeX macro `\over`
- accents from *amsxtra* package
- macros `\definecolor`, `\textcolor`, `\colorbox` and `\fcolorbox` from the package *color*
- macros `\rotatebox`, `\reflectbox` and `\scalebox` from the package *graphicx*
- most latin, cyrillic and greek characters are available
- commands `\newcommand` and `\newenvironment`
- environments `array`, `matrix`, `pmatrix`, ..., `eqnarray`, `cases`
- vertical and horizontal lines are handled in `array` environment
- commands to change the size of the font are available : `\tiny`, `\small`, ..., `\LARGE`, `\huge`, `\Huge`

Audio

Use the `<object>` DITA element to add audio to your DITA topics. Example:

 [audio.mp3 \(audio/mpeg\)](#)

The XML source code corresponding to the above example is:

```

<p><object data="media/audio.mp3" type="audio/mpeg">
  <param name="source" value="media/audio.ogg"
    valuetype="ref" type="audio/ogg"/>

  <param name="source" value="media/audio.m4a"
    valuetype="ref" type="audio/mp4"/>

  <param name="source" value="media/audio.wav"
    valuetype="ref" type="audio/wav"/>

  <param name="controls" value="true"/>
</object></p>

```

Notes:

- The @data and @type attributes are required. The value of the @type attribute must start with "audio/".
- It is strongly recommended to specify *alternate audio files* as modern web browsers, while all supporting the HTML 5 <audio> element, vary in their support of audio formats. This is done by adding <param> child elements to the <object> element. Such <param> elements must have a name="source" attribute, a valuetype="ref" attribute, a @value attribute referencing an audio file and preferably, a @type attribute specifying the media type of the audio file.
- It is possible to add <param> elements corresponding to the attributes supported by the HTML 5 audio element (<crossorigin>, <preload>, <autoplay>, <mediagroup>, <loop>, <muted>, <controls>). In the above example, we have added a <param> element corresponding to the @controls HTML 5 attribute. Note that in the case of HTML 5 *boolean* attributes (<autoplay>, <loop>, <muted>, <controls>), the @value attribute of a <param> is not significant. For example, in the case of the above example, you could have specified "yes", "on", "1", etc, instead of "true".
- If the <object> element has a <desc> child element, then this <desc> element is used to generate fallback content in case audio is not supported. If the object element has no <desc> child element, then a simple fallback content is automatically generated by ditac. This automatic fallback content basically consists in a link allowing to download the audio file.
- When ditac is used to generate an XSL-FO based format (PDF, RTF, etc), only the fallback content appears in the output file.
- [Lightweight DITA](#) has an <audio> element, so there is no need to use an <object> element. The equivalent of the above <object> example would be:

```

<audio>
  <media-controls value="true"/>

  <media-source value="media/audio.mp3"/>
  <media-source value="media/audio.ogg"/>
  <media-source value="media/audio.m4a"/>
  <media-source value="media/audio.wav"/>
</audio>

```

Video

Use the <object> DITA element to add video to your DITA topics. Example:



[video.mp4 \(video/mp4\)](#)

The XML source code corresponding to the above example is:

```
<p><object data="media/video.mp4" type="video/mp4">
  <param name="source" value="media/video.ogv"
    valuetype="ref" type='video/ogg; codecs="theora, vorbis"'/>

  <param name="source" value="media/video.webm"
    valuetype="ref" type="video/webm"/>

  <param name="width" value="320"/>
  <param name="controls" value="yes"/>
  <param name="poster" value="media/video_poster.jpg"
    valuetype="ref"/>
</object></p>
```

Notes:

- The @data and @type attributes are required. The value of the @type attribute must start with "video/".
- It is strongly recommended to specify *alternate video files* as modern web browsers, while all supporting the HTML 5 <video> element, vary in their support of video formats. This is done by adding <param> child elements to the <object> element. Such <param> elements must have a name="source" attribute, a valuetype="ref" attribute, a @value attribute referencing a video file and preferably, a @type attribute specifying the media type of the video file.
- It is possible to add <param> elements corresponding to the attributes supported by the HTML 5 <video> element (<crossorigin>, <poster>, <preload>, <autoplay>, <mediagroup>, <loop>, <muted>, <controls>, <width>, <height>). In the above example, we have added a <param> element corresponding to the <width>, <controls> and <poster> HTML 5 attributes. Note that in the case of HTML 5 *boolean* attributes (<autoplay>, <loop>, <muted>, <controls>), the @value attribute of a <param> is not significant. For example, in the case of the above example, you could have specified "true", "on", "1", etc, instead of "yes".
- If the <object> element has a <desc> child element, then this <desc> element is used to generate fallback content in case video is not supported. If the object element has no <desc> child element, then a simple fallback content is automatically generated by ditac. This automatic fallback content basically consists in a link allowing to download the video file. The <param> element corresponding to the <poster> HTML 5 attribute, if present, is used to generate a nicer automatic fallback content.
- When ditac is used to generate an XSL-FO based format (PDF, RTF, etc), only the fallback content appears in the output file.
- **Lightweight DITA** has an <video> element, so there is no need to use an <object> element. The equivalent of the above <object> example would be:

```
<video width="320">
  <video-poster value="media/video_poster.jpg"/>

  <media-controls value="true"/>

  <media-source value="media/video.mp4"/>
```

```
<media-source value="media/video.ogv"/>
<media-source value="media/video.webm"/>
</video>
```

Other uses of the <object> element

We have seen in previous sections how the <object> DITA element may be used to add audio and video to your DITA topics. In any case other than those described in previous sections, the <object> DITA element is converted to the equivalent <object> XHTML element. For example, if you want to add a YouTube video to your DITA topics, simply do it in DITA as you would do it in XHTML using the <object> element.

 Watch this [test video](#) on YouTube.

The XML source code corresponding to the above example is:

```
<p><object data="https://www.youtube.com/embed/C0DPdy98e4c"
width="640" height="360">
  <desc><image href="media/youtube_icon.png"/> Watch this <xref format="html"
href="https://youtu.be/C0DPdy98e4c" scope="external">test video</xref> on
  YouTube.</desc>
</object></p>
```

Notes:

- If the <object> element has a <desc> child element, then this <desc> element is used to generate fallback content in case the media object is not supported. If the object element has no <desc> child element, then a simple fallback content is automatically generated by ditac. This automatic fallback content basically consists in a link allowing to download the media file.
- When ditac is used to generate an XSL-FO based format (PDF, RTF, etc), only the fallback content appears in the output file.

Part II. Customizing the output of XMLmind DITA Converter

How to customize the output of XMLmind DITA Converter beyond what can be done with XSLT stylesheet parameters alone. For XML experts.

Chapter 9. Simple customization

1. Customize the look of the (X)HTML pages generated by ditac

We'll explain how to customize the look of the (X)HTML pages generated by ditac by using an example. Let's suppose we want to render topic titles in a nice dark blue color rather than in black.

About this task

The easiest way to customize the look of the (X)HTML pages generated by ditac is to use a custom CSS stylesheet rather than the stock one.

Procedure

1. Create a custom CSS stylesheet importing the stock CSS stylesheet.

The stock CSS stylesheet is found in:

`ditac_install_dir/xsl/xhtml/resources/base.css`

Used for the XHTML 1.0, XHTML 1.1, HTML 4.01 and XHTML 5 output formats.

`ditac_install_dir/xsl/webhelp/resources/base.css`

Used for the Web Help output format.

`ditac_install_dir/xsl/htmlhelp/resources/base.css`

Used for the HTML Help output format.

`ditac_install_dir/xsl/eclipsehelp/resources/base.css`

Used for the Eclipse Help output format.

`ditac_install_dir/xsl/epub/resources/base.css`

Used for the EPUB output format.

Initial contents of the custom CSS stylesheet (a copy of this file is found in [customize/custom.css](#)).

```
@import url(base.css);
```



Restriction

Microsoft HTML Help viewer hh.exe does not support @import. Therefore you must *copy* base.css into your custom CSS stylesheet if you generate HTML Help.

2. Add one or more rules to the custom CSS stylesheet.

The XSLT stylesheets generating (X)HTML pages make extensive use of the class attribute. Generally the XHTML element generated for a DITA element has a class attribute bearing the name of the DITA element. Example: a DITA <p> is converted to a XHTML <div class="p">.

For more information, you'll have to refer to the stock CSS stylesheet or even to the (X)HTML pages generated by ditac.

```
@import url(base.css);

.part-title,
```

```
.chapter-title,
.appendix-title,
.section1-title,
.section2-title,
.section3-title,
.section4-title,
.section5-title,
.section6-title,
.section7-title,
.section8-title,
.section9-title,
.topic-title {
    color: #403480;
    border-bottom: 2px solid #403480;
}
```

3. Specify the "-p `custom-css` `customize/custom.css`" option when running `ditac`.

```
$ ditac -images img -p xsl-resources-directory res \
    -p custom-css customize/custom.css \
    out/manual/_html manual.ditamap
```

The above command gives the expected results because:

1. "-p `xsl-resources-directory res`" copies all stock resources, including `base.css`, to subdirectory `out/manual/res/`.
2. "-p `custom-css customize/custom.css`" copies `custom.css` to subdirectory `out/manual/res/`.

2. Customizing the look of the PDF files generated by ditac

We'll explain how to customize the look of the PDF files generated by `ditac` by using an example. Let's suppose we want to render topic titles in a nice dark blue color rather than in black.

About this task

A PDF file is created by converting the XSL-FO file generated by the `ditac` XSLT 2.0 stylesheet by the means of an XSL-FO processor such as Apache FOP, RenderX XEP or Antenna House Formatter. Therefore we need to generate a custom XSL-FO file. This is done by creating a very simple variant of the stock XSLT stylesheet which generates XSL-FO.

Procedure

1. Create a custom XSLT stylesheet importing the stock one.

This stock XSLT stylesheet is found in `ditac_install_dir/xsl/fo/fo.xsl`. It is used to generate an intermediate XSL-FO file. After that, the XSL-FO file is converted to PDF, PostScript, RTF, WordprocessingML, Office Open XML (.docx) or OpenOffice/LibreOffice (.odt) by the means of an XSL-FO processor.

Initial contents of the custom XSLT stylesheet (a copy of this file is found in `customize/custom_fo.xsl`).

```
<xsl:stylesheet xmlns:xsl="http://www.w3.org/1999/XSL/Transform"
    xmlns:fo="http://www.w3.org/1999/XSL/Format"
    version="2.0">
```

```
<xsl:import href="ditac-xsl:fo/fo.xsl"/>

</xsl:stylesheet>
```

Notice the funny looking URI "ditac-xsl:fo/fo.xsl". "ditac-xsl:" is an easy way to refer to *ditac_install_dir*/xsl/. This works because the XML catalog used by the **ditac** command-line utility (found in *ditac_install_dir*/schema/catalog.xml) contains:

```
<rewriteURI uriStartString="ditac-xsl:" rewritePrefix="../xsl/" />
```

2. Redefine one or more named xsl:attribute-sets in your custom XSLT stylesheet.

Named xsl:attribute-sets are not documented yet. For more information, you'll have to refer to the XSLT stylesheets found in *ditac_install_dir*/xsl/fo/.

```
<xsl:stylesheet xmlns:xsl="http://www.w3.org/1999/XSL/Transform"
  xmlns:fo="http://www.w3.org/1999/XSL/Format"
  version="2.0">

  <xsl:import href="ditac-xsl:fo/fo.xsl"/>

  <xsl:attribute-set name="topic-title" use-attribute-sets="topic-title">
    <xsl:attribute name="color">#403480</xsl:attribute>
    <xsl:attribute name="font-size">160%</xsl:attribute>
    <xsl:attribute name="padding-bottom">0.05em</xsl:attribute>
    <xsl:attribute name="border-bottom">0.5pt solid #403480</xsl:attribute>
    <xsl:attribute name="space-before.optimum">1.5em</xsl:attribute>
    <xsl:attribute name="space-before.minimum">1.2em</xsl:attribute>
    <xsl:attribute name="space-before.maximum">1.8em</xsl:attribute>
  </xsl:attribute-set>

</xsl:stylesheet>
```

3. Specify the "-t customize/custom_fo.xsl" option when running ditac.

```
$ ditac -t customize/custom_fo.xsl \
  out/manual.pdf manual.ditamap
```

Alternatively, package your custom XSLT stylesheet as a [plug-in](#) and then specify the name of this plug-in using the **-plugin** command-line option. By doing this, your custom XSLT stylesheet will be automatically used whatever the output format which uses XSL-FO as its intermediate format (PDF, RTF, .odt, .docx, etc).

Chapter 10. Using ditac to convert documents conforming to a DITA specialization

We'll explain by example how to use ditac to convert documents conforming to a DITA specialization. Let's suppose we have a DITA specialization which adds `<time>` and `<kbd>` elements (similar to `<time>` and `<kbd>` HTML5 elements) topic contents. These elements are modeled as follows (see [sample_plugin/dtd/sampleDomain.mod](#))

```
<!ENTITY % time "time">

<!ELEMENT time (#PCDATA | %text;)*>

<!ATTLIST time %univ-atts;
              outputclass CDATA #IMPLIED>

<!ATTLIST time %global-atts;
              class CDATA "+ topic/ph sample-d/time ">

<!ATTLIST time %univ-atts;
              datetime CDATA #IMPLIED>

<!ENTITY % kbd "kbd">

<!ELEMENT kbd (#PCDATA | %text;)*>

<!ATTLIST kbd %univ-atts;
              outputclass CDATA #IMPLIED>

<!ATTLIST kbd %global-atts;
              class CDATA "+ topic/ph sample-d/kbd ">
```

All the example files of this tutorial have been packaged as a [plug-in](#) called "sample_plugin". They are found in directory [sample_plugin/](#). In order to give this plug-in a try, you'll have to copy directory `sample_plugin/` to `ditac_install_dir/plugin/`.

About this task

Using ditac to convert documents conforming to a DITA specialization basically requires customizing the output of the tool using the same techniques as those explained in [Chapter 9, Section 1](#) and [Chapter 9, Section 2](#).

Procedure

1. Create an XML catalog pointing to a local copy of your custom DTD. This file must be named `catalog.xml` and must be found in your plug-in directory.

File `sample_plugin/catalog.xml`:

```
<catalog xmlns="urn:oasis:names:tc:entity:xmlns:xml:catalog"
         prefer="public">

  <public publicId="-//OASIS//DTD DITA Concept//EN"
         uri="dtd/concept.dtd"/>
```

```

<public publicId="-//OASIS//DTD DITA Composite//EN"
        uri="dtd/ditabase.dtd"/>

<public publicId="-//OASIS//DTD DITA General Task//EN"
        uri="dtd/generalTask.dtd"/>

...

</catalog>

```

2. Create a customization of *ditac_install_dir/xsl/xhtml1/xhtml1.xsl* as explained in [Chapter 9, Section 2](#). This file must be found in *your_plugin_dir/xsl/xhtml1/xhtml1.xsl* in order to be used by ditac.

File *sample_plugin/xsl/xhtml1/xhtml1.xsl*:

```

<xsl:stylesheet xmlns:xsl="http://www.w3.org/1999/XSL/Transform"
                xmlns="http://www.w3.org/1999/xhtml1"
                version="2.0">

  <xsl:import href="ditac-xsl/xhtml1/xhtml1.xsl"/>
  <xsl:param name="cssResourceName" select="'xhtml.css'"/>

  <xsl:template match="*[contains(@class, ' sample-d/kbd ')]">
    <tt>
      <xsl:call-template name="commonAttributes"/>
      <xsl:apply-templates/>
    </tt>
  </xsl:template>

  <xsl:template match="*[contains(@class, ' sample-d/time ')]">
    <span>
      <xsl:call-template name="commonAttributes"/>
      <xsl:apply-templates/>
    </span>
  </xsl:template>

</xsl:stylesheet>

```

Note that the XSLT template called `commonAttributes` adds a `class="kbd"` attribute to the generated `<tt>` element. Similarly, it adds a `class="time"` attribute to the `<span>` element generated for the `<time>` element. So how to style the generated `<tt class="kbd">` and `<span class="time">`?

- a. Copy *ditac_install_dir/xsl/xhtml1/resources/* and *ditac_install_dir/xsl/xhtml1/resources.list* to *your_plugin_dir/xsl/xhtml1/*.
- b. Copy the following `xhtml.css` CSS stylesheet to *your_plugin_dir/xsl/xhtml1/resources/*.

```

@import url(base.css);

.kbd {
  font-family: monospace;
  font-size: 90%;
}

```

```

border: 1px solid #C0C0C0;
border-radius: 3px;
-moz-border-radius: 3px;
-webkit-border-radius: 3px;
padding: 2px;
background-color: #F0F0F0;
}

.time {
background-color: #FFFFCC;
padding: 2px;
}

```

- c. Append the following line to *your_plugin_dir*/xsl/xhtml/resources.list.

```
resources/xhtml.css
```

- d. Declare that the default CSS stylesheet is *xhtml.css* and not *stock base.css*. This is done by using XSLT stylesheet parameter *cssResourceName*.

```

<xsl:stylesheet xmlns:xsl="http://www.w3.org/1999/XSL/Transform"
                xmlns="http://www.w3.org/1999/xhtml"
                version="2.0">

  <xsl:import href="ditac-xsl/xhtml/xhtml.xsl"/>
  <xsl:param name="cssResourceName" select="'xhtml.css'"/>
  ...

```

3. Create a customization of *ditac_install_dir*/xsl/fo/fo.xsl as explained in [Chapter 9, Section 2](#). This file must be found in *your_plugin_dir*/xsl/fo/fo.xsl in order to be used by ditac.

File *sample_plugin*/xsl/fo/fo.xsl:

```

<xsl:stylesheet xmlns:xsl="http://www.w3.org/1999/XSL/Transform"
                xmlns:fo="http://www.w3.org/1999/XSL/Format"
                version="2.0">

  <xsl:import href="ditac-xsl:fo/fo.xsl"/>

  <xsl:attribute-set name="kbd" use-attribute-sets="monospace-style">
    <xsl:attribute name="border">1px solid #C0C0C0</xsl:attribute>
    <xsl:attribute name="background-color">#F0F0F0</xsl:attribute>
    <xsl:attribute name="padding">0.25em</xsl:attribute>
  </xsl:attribute-set>

  <xsl:template match="*[contains(@class,' sample-d/kbd ')]">
    <fo:inline xsl:use-attribute-sets="kbd">
      <xsl:call-template name="commonAttributes"/>
      <xsl:apply-templates/>
    </fo:inline>
  </xsl:template>

  ...

```

```
</xsl:stylesheet>
```

4. Pass command-line option **-plugin** *plugin_name* to **ditac** in order to use the DTDs (or schemas) and the XSLT stylesheets found in your plug-in subdirectory, preferably to those found in *ditac_install_dir/schema/* and in *ditac_install_dir/xsl/*.

You'll find a sample DITA document making use of the custom `<time>` and `<kbd>` elements in [sample_plugin/sample/sample.ditamap](#). You can convert this sample document to single-page XHTML and to PDF by running `sample_plugin/sample/run.sh` (`sample_plugin\sample\run.bat` on Windows):

```
../../../../bin/ditac -plugin sample_plugin \  
    out/sample.pdf sample.ditamap
```

Chapter 11. Extensive customization

In order to extensively customize the output of ditac, you need to learn how it works.

Basically, this means that you'll have to understand the contents of the `ditac_lists.ditac_list` file and the `.ditac` files, which are generated by the ditac *preprocessor*.

An extensive customization works exactly like a simple one:

1. Create a custom XSLT 2.0 stylesheet which imports the stock one.
2. Redefine one or more attribute sets and/or one or more templates in the custom XSLT 2.0 stylesheet.


The only difference is that this time, you need to know exactly what is the format of the files you are going to transform. The bad news first: the ditac XSLT 2.0 stylesheets do not transform plain DITA files. They transform `.ditac` files, which are *fully preprocessed DITA files*. Now, the good news: `.ditac` files mainly contains DITA elements and because the ditac preprocessor performs all the grunt work beforehand, `.ditac` files are really straightforward to transform.

In fact, transforming `.ditac` files rather than plain DITA files allows to concentrate on creating great-looking output.

How it works

The ditac preprocessor generates a single `ditac_lists.ditac_list` file and one or more `.ditac` files⁽¹¹⁾ out of the source DITA files.

Figure 11-1. The intermediate files generated by the ditac preprocessor



Then, each `.ditac` file, which mainly contains fully preprocessed DITA topics, is transformed in turn by the ditac XSLT 2.0 stylesheets.

The `ditac_lists.ditac_list` file, which contains useful information about the overall DITA document being converted, is not directly transformed by the ditac XSLT 2.0 stylesheets. Instead, when needed to, the ditac XSLT 2.0 stylesheets *query* the `ditac_lists.ditac_list` file in order to generate optional items. Example: number topics, tables, figures, etc, when parameter `number='XXX'` has been specified.

It is possible to examine the contents of the `ditac_lists.ditac_list` file and those of the `.ditac` files by specifying the **-preprocess** command-line option. Example:

```
$ ditac -preprocess \
-v -chunk single \
-images img -p xsl-resources-directory res \
out/manual.html manual.ditamap
```

⁽¹¹⁾A single `.ditac` file for a print output; one or more `.ditac` files for a screen output.

Contents of a .ditac file

The root element of a .ditac file is `<ditac:chunk>`. A `<ditac:chunk>` element may have the following child elements (in any order and in any number):

`<ditac:titlePage>`

This empty placeholder element means: generate a "title page" section here.

`<ditac:toc>`

This empty placeholder element means: generate a **Table of Contents** section here.

`<ditac:figureList>`

This empty placeholder element means: generate a **List of Figures** section here.

`<ditac:tableList>`

This empty placeholder element means: generate a **List of Tables** section here.

`<ditac:exampleList>`

This empty placeholder element means: generate a **List of Examples** section here.

`<ditac:equationList>`

This empty placeholder element means: generate a **List of Equations** section here.

`<ditac:indexList>`

This empty placeholder element means: generate an **Index** section here.

A DITA topic of any kind

A fully preprocessed topic. This topic is guaranteed not to contain nested topics.

`<ditac:flags-block>`

`<ditac:flags-inline>`

Wrapper elements used to implement *flagging* in ditac. Flagging is specified by the means of a conditional processing profile (a .ditaaval file). See also [the -filter command-line option](#).

- A DITA block element which supports all flagging features⁽¹²⁾ is wrapped in a `<ditac:flags-block>` element having flagging attributes such as `@color`, `@text-decoration`, `@change-bar-placement`, etc.
- A DITA inline element which supports all flagging features⁽¹³⁾ is wrapped in a `<ditac:flags-inline>` element having flagging attributes such as `@color`, `@text-decoration`, `@startImage`, etc.
- Any other DITA element is considered not to support all flagging features and as such, is given *flagging attributes* like `@ditac:flags-color`, `@ditac:flags-background-color`, `@ditac:flags-font-weight`, etc, rather than being wrapped in a `<ditac:flags-block>` or `<ditac:flags-inline>` element.

More formally, the content model of `<ditac:chunk>` is specified by the [schema/ditac.rnc](#) RELAX NG grammar.

Example:

```
<ditac:chunk xmlns:ditac="http://www.xmlmind.com/ditac/schema/ditac"
  xmlns:ditaarch="http://dita.oasis-open.org/architecture/2005/">
```

⁽¹²⁾That is, `<topic>`, `<p>`, `<lq>`, `<note>`, `<dl>`, `<ul>`, `<ol>`, `<sl>`, `<pre>`, `<lines>`, `<fig>`, `<object>`, `<table>`, `<simplatable>`, `<section>`, `<example>` and their specializations.

⁽¹³⁾That is, `<ph>`, `<term>`, `<xref>`, `<cite>`, `<q>`, `<boolean>`, `<state>`, `<keyword>`, `<tm>`, `<image>`, `<foreign>` and their specializations.

```

<ditac:titlePage/>
<ditac:toc/>
<topic class="- topic/topic "
    domains="(topic ui-d) (topic hi-d) (topic pr-d) (topic sw-d)
            (topic ut-d) (topic indexing-d)"
    id="introduction" ditaarch:DITAArchVersion="1.1">
    <title class="- topic/title ">Introduction</title>
    .
    .
    .
</topic>
<topic class="- topic/topic " id="I_2yl4p_">
    <title class="- topic/title ">Using XMLmind DITA Converter</title>
</topic>
<task class="- topic/topic task/task "
    domains="(topic ui-d) (topic hi-d) (topic pr-d) (topic sw-d)
            (topic ut-d) (topic indexing-d)"
    id="install" ditaarch:DITAArchVersion="1.1">
    <title class="- topic/title ">Installing XMLmind DITA Converter</title>
    .
    .
    .
</task>
.
.
.
<ditac:indexList/>
</ditac:chunk>

```



Important

The DITA topics contained in a .ditac file are fully preprocessed. What does this mean? Basically that they are ready to be transformed without further efforts:

- Conref inclusions have been processed.
- Unspecified attributes having default values have been added to the elements. Example: a <p> element becomes <p class="- topic/p ">.
- Elements now have a ``flat'', globally unique, ID. Example: the @id attribute of this <title> element <topic id="introduction"><title id="start"> becomes id="introduction__start".
- The @href attribute of <xref>, <link>, <image>, <svgref>, <mathmlref> elements now point to the (future) output files. Example: the @href attribute of this <xref> element <xref href="intro.dita#introduction/start"> becomes href="userguide-1.html#introduction__start".
- Some text may have been added to empty <xref> and <link> elements.
- The <reltable> elements of the DITA map have been converted to <related-links> sections or to extra <link> elements.

- Filtered elements have been removed. Flagged elements have been wrapped in a `<ditac:flags>` element.

Contents of the `ditac_lists.ditac_list` file

The root element of the `ditac_lists.ditac_list` file is `<ditac:lists>`. A `<ditac:lists>` element may have the following child elements (in this exact order and in this exact number):

`<ditac:chunkList>`

A `<ditac:chunkList>` contains a `<ditac:chunk>` element for each `.ditac` file. A `<ditac:chunk>` element may be seen as the *manifest* of a `.ditac` file.

Example:

```
<ditac:chunkList>
  <ditac:chunk file="manual.html">
    <ditac:titlePage/>
    <ditac:toc/>
    <ditac:topic id="introduction" number="bookabstract.1"
      role="bookabstract" title="Introduction"/>
    .
    .
    .
    <ditac:topic id="limitations" number="appendix.1" role="appendix"
      title="Limitations and implementation specificities"/>
    <ditac:indexList/>
  </ditac:chunk>
</ditac:chunkList>
```

`<ditac:titlePage>`

Contains all the DITA elements needed to generate the "title page" section of a document. This element exists but is empty if the DITA document being converted has no title and no metadata (e.g. `<topicmeta>`/`<autor>`, `<bookmeta>`/`<publisherinformation>`, etc).

Example:

```
<ditac:titlePage>
  <title class="- topic/title ">XMLmind DITA Converter Manual</title>
  <bookmeta class="- map/topicmeta bookmap/bookmeta ">
    <authorinformation class="+ topic/author xnal-d/authorinformation ">
      .
      .
      .
    <critdates class="- topic/critdates ">
      <created class="- topic/created " date="September 17, 2009"/>
    </critdates>
  </bookmeta>
</ditac:titlePage>
```

`<ditac:frontmatterTOC>`

`<ditac:toc>`

`<ditac:backmatterTOC>`

Contains all the information needed to generate **Table of Contents** section of a document.

Example:

```
<ditac:toc>
  <ditac:tocEntry file="manual.html" id="I_2yl4p_" number="part.1"
    role="part" title="Using XMLmind DITA Converter">
    <ditac:tocEntry file="manual.html" id="install"
      number="part.1 chapter.1" role="chapter"
      title="Installing XMLmind DITA Converter">
      .
      .
      .
    </ditac:tocEntry>
  </ditac:tocEntry>
  <ditac:tocEntry file="manual.html" id="limitations" number="appendix.1"
    role="appendix"
    title="Limitations and implementation specificities"/>
</ditac:toc>
```

<ditac:figureList>

Contains all the information needed to generate the **List of Figures** section of a document. This element exists but is empty if the DITA document being converted contains no <fig> elements having a <title> child element.

Example:

```
<ditac:figureList>
  <ditac:figure file="manual.html" id="xsltParams__page_areas"
    number="part.1 chapter.4 figure.1" title="Page areas"/>
  <ditac:figure file="manual.html" id="howItWorks__I_6gb2s_"
    number="part.2 chapter.3 figure.1"
    title="The intermediate files generated by
      the ditac preprocessor"/>
</ditac:figureList>
```

<ditac:tableList>

Contains all the information needed to generate the **List of Tables** section of a document. This element exists but is empty if the DITA document being converted contains no <table> elements having a <title> child element.

Example:

```
<ditac:tableList>
  <ditac:table file="manual.html"
    id="quickStart__supported_filename_extensions"
    number="part.1 chapter.2 table.1"
    title="Supported filename extensions"/>
  <ditac:table file="manual.html"
    id="quickStart__supported_output_formats"
    number="part.1 chapter.2 table.2"
    title="Supported output formats"/>
</ditac:tableList>
```

<ditac:exampleList>

Contains all the information needed to generate the **List of Examples** section of a document. This element exists but is empty if the DITA document being converted contains no <example> elements having a <title> child element.

Example:

```
<ditac:exampleList>
  <ditac:example file="topicAAA.htm" id="topicAAA__I_6wcr3_"
    number="part.1 example.1" title="Example AAA.1"/>
  .
  .
  .
  <ditac:example file="topicHHH.htm" id="topicHHH__exampleHHH.2"
    number="appendix.2 example.2" title="Example HHH.2"/>
</ditac:exampleList>
```

<ditac:equationList>

Contains all the information needed to generate the **List of Examples** section of a document. This element exists but is empty if the DITA document being converted contains no <equation-fig-ure> elements having a <title> child element.

Example:

```
<ditac:equationList>
  <ditac:equation file="part222.html" id="part222__first_equation"
    number="part.2 equation.1" title="First equation">
    <ditac:description>This is a short description of the first equation.
    It should be displayed in the <i class="+ topic/ph hi-d/i ">
    <b class="+ topic/ph hi-d/b ">List of
    Equations</b></i>.</ditac:description>
  </ditac:equation>
  .
  .
  .
  <ditac:equation file="trademarks.html" id="trademarks__I_qa9vmk_"
    number="equation.4" title="Second equation"/>
</ditac:equationList>
```

<ditac:indexList>

Contains all the information needed to generate the **Index** section of a document. This element exists but is empty if the DITA document being converted contains no <indexterm> elements.

Example:

```
<ditac:indexList>
  <ditac:div title="A">
    <ditac:indexEntry term="appendix-number-format, parameter"
      xml:id="I_hd1wr_">
      <ditac:indexAnchor file="manual.html"
        id="xsltParams__I_8bona_"
        number="1"/>
    </ditac:indexEntry>
    <ditac:indexEntry sortAs="automap" term="-automap, option"
      xml:id="I_2gud9_">
```

```

        <ditac:indexAnchor file="manual.html"
                           id="commandLine__I_5x8va_"
                           number="1"/>
    </ditac:indexEntry>
</ditac:div>
.
.
.
<ditac:div title="X">
.
.
.
    <ditac:indexEntry sortAs="xslt" term="-xslt, option"
                      xml:id="I_atn9k_">
        <ditac:indexAnchor file="manual.html"
                           id="commandLine__I_cu3ew_"
                           number="1"/>
        <ditac:indexAnchor file="manual.html"
                           id="customAttributeSet__I_gis5b_" number="2"/>
        <ditac:indexAnchor file="manual.html"
                           id="specialize__I_11514_"
                           number="3"/>
        <ditac:indexSeeAlso ref="I_bhy05_" term="-t, option"/>
        <ditac:indexSeeAlso ref="I_f1jh_" term="-xslt, option"/>
    </ditac:indexEntry>
</ditac:div>
</ditac:indexList>

```

More formally, the content model of `<ditac:lists>` is specified by the [schema/ditac_lists.rnc](#) RELAX NG grammar.

Currently the `ditac_lists.ditac_list` file is used to generate:

- the "title page" section of a document;
- the **Table of Contents** section of a document;
- the **List of Figures**, **List of Tables**, **List of Examples**, **List of Equations** sections of a document;
- the **Index** section of a document;
- the navigation icons in a multi-page HTML document;
- all the files (`project.php`, `toc.hhc`, etc) required by the HTML Help system;
- all the files (`jhelpset.hs`, `jhelpmap.jhm`, etc) required by the Java™ Help system.

Part III. Embedding XMLmind DITA Converter in a Java™ application

Invoke XMLmind DITA Converter from your Java application without having to execute **ditac**, an external command-line tool. For Java programmers.

Chapter 12. High-level method: embedding `com.xmlmind.ditac.convert.Converter`

Quick and easy embedding: embed `com.xmlmind.ditac.convert.Converter`, the Java™ class which is used to implement the **ditac** command-line utility.

`Converter` is the object which is at the core of the **ditac** command-line utility. Its `run` method accepts the same string arguments as the **ditac** command-line utility.

The full source code of the Embed1 sample is found in `Embed1.java`.

1. Create the Converter.

```
StyleSheetCache cache = new StyleSheetCache();

Console console = new Console() {
    public void showMessage(String message, MessageType messageType) {
        System.err.println(message);
    }
};

Converter converter = new Converter(cache, console);
```

- `StyleSheetCache` is a simple cache for the ditac XSLT 2.0 stylesheets. It is a thread-safe object which is intended to be shared by several `Converters`.

Unlike `StyleSheetCache`, `Converter` is not thread-safe. Each thread must own its `Converter`. However, the `run` method of a `Converter` may be invoked several times.

- `Console` is a very simple interface. Implementing this interface allows to do whatever you want with the messages reported by a `Converter`.

2. Configure the Converter.

```
converter.registerFOP(new File("/opt/fop/fop"), /*configFile*/ null);
```

There are several methods which may be used to register an XSL-FO processor with a `Converter`. From high-level ones to low-level ones, these methods are: `registerFOP`, `registerXEP`, `registerAHF`, `registerXFC`, `registerExternalFOConverter`, `registerFOConverter`.

3. Invoke the run method.

```
String[] args = {
    "-v",
    "-p", "number", "all",
    outFile.getPath(),
    inFile.getPath(),
};

return converter.run(args);
```

The `run` method returns 0 if the conversion is successful and an integer greater than 0 otherwise. When the conversion fails, errors messages are displayed on the `Console`.

Environment required for running this kind of embedding

Aside ".jar" files like `ditac.jar`, `xmlresolver.jar`, `saxon12.jar`, etc, which are all listed in `ditac_install_dir/doc/manual/embed/build.xml` (see below), this kind of embedding also needs to access:

- The DITA DTD, schemas and XML catalogs normally found in `ditac_install_dir/schema/`.
- The XSL stylesheets normally found in `ditac_install_dir/xsl/`.

Therefore the requirements for running this kind of embedding are:

1. Use system property `xml.catalog.files` to point to `ditac_install_dir/schema/catalog.xml` or to an equivalent of this XML catalog.
2. Stock `ditac_install_dir/schema/catalog.xml` contains the following entry:

```
<rewriteURI uriStartString="ditac-xsl:" rewritePrefix="../../../xsl/" />
```

This `<rewriteURI>` entry is needed to find the location of the directory containing the XSL stylesheets. Make sure that this entry exists in your XML catalogs and that it points to the actual location of the directory containing the XSL stylesheets.

Compiling and executing the Embed1 sample

Compile the Embed1 sample by running **ant** in `ditac_install_dir/doc/manual/embed/`.

Execute the Embed1 sample by running **ant** `embed1` in `ditac_install_dir/doc/manual/embed/`. This will convert `ditac_install_dir/docsrc/manual/manual.ditamap` to `ditac_install_dir/doc/manual/embed/manual.pdf`, using Apache FOP.

Note that `Embed1.java` contains “hardwired filenames” like `"/opt/fop/fop"`. This means that, without modifications, this sample cannot be run from elsewhere than `ditac_install_dir/doc/manual/embed/` and that you'll almost certainly need to modify the source code in order to specify the actual location of the `fop` (`fop.bat`) script.

Related information

- [Chapter 13. Advanced low-level embedding method](#)

Chapter 13. Low-level method: embedding `com.xmlmind.ditac.preprocess.PreProcessor`

Advanced embedding method: first invoke a preprocessor which will generate intermediate `.ditac` files, then invoke the XSLT 2.0 engine in order to transform all these `.ditac` files.

This method consists in first invoking the `PreProcessor` in order to pre-process the DITA source files into a `ditac_lists.ditac_lists` file and one or more `.ditac` files; then invoking the `Saxon` XSLT 2.0 engine in order to transform all the `.ditac` files.

For some output formats, PDF, RTF, etc, the final third step consists in invoking an XSL-FO processor such as `Apache FOP` in order to convert the XSL-FO generated by the XSLT stylesheets to the desired output format.

The full source code of the `Embed2` sample is found in `Embed2.java`.

1. Invoke the `ditac PreProcessor` to pre-process the DITA source files into a `ditac_lists.ditac_lists` file and one or more `.ditac` files.

- 1.a. Create and configure the `PreProcessor`.

```
Console console = new Console() {
    public void showMessage(String message, MessageType messageType) {
        System.err.println(message);
    }
};

PreProcessor preProc = new PreProcessor(console);
preProc.setChunking(Chunking.SINGLE);
preProc.setMedia(Media.SCREEN);

ResourceHandlerBase resHandler = new ResourceHandlerBase();
resHandler.parseParameters("img");
preProc.setResourceHandler(resHandler);
```

- `Console` is a very simple interface. Implementing this interface allows to do whatever you want with the messages reported by a `PreProcessor`.
- Specifying `preProc.setChunking(Chunking.SINGLE)` allows to generate a single HTML page using a DITA map designed to generate multiple HTML pages.
- A `PreProcessor` is not concerned about the *exact* output format. However its behaves differently depending on the target `Media`.
- A `PreProcessor` handles to an `ResourceHandler` all the resource files, typically image files, referenced in the DITA source using relative URLs. An `ResourceHandler` is registered with a `PreProcessor` using method `setResourceHandler`.

In the case of the `Embed2` sample, we use the simplest possible `ResourceHandler` which is `ResourceHandlerBase`.

- 1.b. Pre-process the DITA source files.

```
URL inFileURL = null;
try {
    inFileURL = inFile.toURI().toURL();
} catch (MalformedURLException cannotHappen) {}
```

```

File[] preProcFiles = null;
try {
    preProcFiles = preProc.process(new URL[] { inFileURL }, outFile);
} catch (IOException e) {
    console.showMessage(e.toString(), Console.MessageType.ERROR);
}
if (preProcFiles == null) {
    return false;
}

```

The `process` method of a `PreProcessor` returns null if an error other than an `IOException` has caused the pre-processing to fail. When this is the case, errors messages are displayed on the Console.

Note that a `PreProcessor` is not thread-safe. Each thread must own its `PreProcessor`. However, the `process` method of a `PreProcessor` may be invoked several times.

2. Invoke the Saxon XSLT 2.0 engine, in order to transform all the `.ditac` files. Note that this is done using the standard [JAXP](#) API.
 - 2.a. Pass *required system parameters* to the XSLT stylesheets, in addition to the normal, user, parameters.

```

String ditacListsURI = "";

int count = preProcFiles.length;
for (int i = 0; i < count; ++i) {
    File ditacFile = preProcFiles[i];

    if (ditacFile.getPath().endsWith(DITAC_LISTS_SUFFIX)) {
        ditacListsURI = ditacFile.toURI().toASCIIString();
        break;
    }
}

String[] params = {
    "ditacListsURI", ditacListsURI,
    "xsl-resources-directory", "res",
    "use-note-icon", "yes",
    "default-table-width", "100%"
};

```

These required system parameters are:

- `ditacListsURI`, always required.
 - `foProcessor`, required by the XSLT stylesheets that generate XSL-FO.
 - `chmBasename`, `hhpBasename`, required by the XSLT stylesheets that generate HTML Help.
- 2.b. Use the Saxon XSLT 2.0 engine to create a `TransformerFactory`, then configure this `TransformerFactory`.

```
private static
```

```

TransformerFactory createTransformerFactory(URIResolver uriResolver,
                                           ErrorListener errorListener)
    throws Exception {
    Class<?> cls = Class.forName("net.sf.saxon.TransformerFactoryImpl");
    TransformerFactory transformerFactory =
        (TransformerFactory) cls.newInstance();

    ExtensionFunctions.registerAll(transformerFactory);

    transformerFactory.setURIResolver(uriResolver);
    transformerFactory.setErrorListener(errorListener);

    return transformerFactory;
}

```

- Creating an instance of Saxon 11 is absolutely needed. XMLmind DITA Converter is not designed to work with any other XSLT engine (e.g. the Xalan XSLT 1.0 engine, which is part of the Java™ runtime).
- The ditac XSLT 2.0 stylesheets make use of a few XSLT extension functions written in Java™. These extension functions must be registered with Saxon. This is done using [ExtensionFunctions.registerAll](#).

2.c. Create and configure a Transformer.

```

private static Transformer createTransformer(String[] params,
                                           Console console)
    throws Exception {
    URIResolver uriResolver = Resolve.getURIResolver();
    ErrorListener errorListener = new ConsoleErrorListener(console);

    TransformerFactory factory = createTransformerFactory(uriResolver,
                                                         errorListener);

    File xslFile = AppUtil.getXSLResourceFile("xhtml/html.xsl");
    Transformer transformer =
        factory.newTransformer(new StreamSource(xslFile));

    transformer.setURIResolver(uriResolver);
    transformer.setErrorListener(errorListener);

    for (int i = 0; i < params.length; i += 2) {
        transformer.setParameter(params[i], params[i+1]);
    }

    return transformer;
}

```

- [Resolve](#) is a helper class making it easy to use the services of [XML Catalog resolvers](#).

By default, [Resolve](#) automatically loads all the XML catalogs specified using the `xml.catalog.files` Java™ system property. Excerpts of the `ant build.xml` file:

```
<target name="embed2" depends="compile,clean_embed2">
```

```
<java classpathref="cp" fork="yes" classname="Embed2">
  <sysproperty key="xml.catalog.files"
    value="${ditac.dir}/schema/catalog.xml" />
  <arg value="${ditac.dir}/docsrc/manual/manual.ditamap" />
  <arg value="manual.html" />
</java>
</target>
```

However, static method `setXMLResolver` allows to configure this thread-safe utility class (used by ditac in many places) differently.

- `ConsoleErrorListener` is an implementation of `ErrorListener` which displays its messages on a Console.
- `AppUtil.getXSLResourceFile` is a utility function used to locate files found in the XSL directory (normally `ditac_install_dir/xsl/`).

2.d. Invoke the Transformer to transform each .ditac file.

```
for (int i = 0; i < count; ++i) {
    File ditacFile = preProcFiles[i];

    String ditacFilePath = ditacFile.getPath();
    if (ditacFilePath.endsWith(DITAC_SUFFIX)) {
        File transformedFile = new File(
            ditacFilePath.substring(0,
                ditacFilePath.length() - DITAC_SUFFIX.length()) +
            ".html");

        try {
            transformer.transform(new StreamSource(ditacFile),
                                new StreamResult(transformedFile));
        } catch (Exception e) {
            console.showMessage(e.toString(),
                               Console.MessageType.ERROR);
            cleanUp(preProcFiles);
            return false;
        }
    }
}
```

In the case of `Embed2`, the above loop is not strictly needed. We specified `preProc.setChunking(Chunking.SINGLE)` and therefore the `PreProcessor` generates a single .ditac file.

3. Copy the resources of the XSLT stylesheets (CSS stylesheets, icons, etc) to output subdirectory `res/`. Note that the images referenced in the DITA source, if any, have already been copied to output subdirectory `img/` by the `ImageCopier`.

```
File dstDir = new File("res");
if (!dstDir.exists()) {
    File srcDir = AppUtil.getXSLResourceFile("xhtml/resources");
    try {
        FileUtil.copyDir(srcDir, dstDir, false);
    } catch (IOException e) {
```

```

        console.showMessage(e.toString(), Console.MessageType.ERROR);
        cleanUp(preProcFiles);
        return false;
    }
}

```

4. Delete the `ditac_lists.ditac_lists` and `.ditac` files.

```
cleanUp(preProcFiles);
```

Environment required for running this kind of embedding

Aside ".jar" files like `ditac.jar`, `xmlresolver.jar`, `saxon12.jar`, etc, which are all listed in *ditac_install_dir/doc/manual/embed/build.xml* (see below), this kind of embedding also needs to access:

- The DITA DTD, schemas and XML catalogs normally found in *ditac_install_dir/schema/*.
- The XSL stylesheets normally found in *ditac_install_dir/xsl/*.

Therefore the requirements for running this kind of embedding are:

1. Use [system property `xml.catalog.files`](#) to point to *ditac_install_dir/schema/catalog.xml* or to an equivalent of this XML catalog.
2. Stock *ditac_install_dir/schema/catalog.xml* contains the following entry:

```
<rewriteURI uriStartString="ditac-xsl:" rewritePrefix="../xsl/" />
```

This `<rewriteURI>` entry is needed to find the location of the directory containing the XSL stylesheets. Make sure that this entry exists in your XML catalogs and that it points to the actual location of the directory containing the XSL stylesheets.

Compiling and executing the Embed2 sample

Compile the Embed2 sample by running **ant** in *ditac_install_dir/doc/manual/embed/*.

Execute the Embed2 sample by running **ant** `embed2` in *ditac_install_dir/doc/manual/embed/*. This will convert *ditac_install_dir/docsrc/manual/manual.ditamap* to single HTML 4.01 page *ditac_install_dir/doc/manual/embed/manual.html*.

Related information

- [Part II, Chapter 11. Extensive customization](#)
- [Chapter 12. Recommended high-level embedding method](#)

Appendix A. About DITA support in XMLmind DITA Converter

DITA 1.3 support

As of version 3.0, XMLmind DITA Converter (ditac for short) fully supports  DITA 1.3 and as such, allows to convert DITA documents conforming to the DITA 1.3 DTD, W3C XML Schema or *RELAX NG schema*. However, there are still limitations, deemed minor, and implementation specificities which are documented in [Appendix C](#).

In fact, when ditac v2.6+ is used, DITA 1.2 documents are automatically “upgraded” to DITA 1.3. This is caused by the fact that the following `<!DOCTYPE>` means “use latest version of the DITA DTD”:

```
<?xml version="1.0" encoding="UTF-8"?>
<!DOCTYPE topic PUBLIC "-//OASIS//DTD DITA Topic//EN" "topic.dtd">
<topic id="MyTopic">
...
</topic>
```

This should not be a problem as DITA 1.3 is a superset of DITA 1.2.

Technical content only

Ditac only supports “Technical content elements”. However [Classification elements](#) (e.g. [subject scheme maps](#)) are still not supported.

DITA 1.3 RELAX NG schema

Ditac has no problem processing a DITA document pointing to a RELAX NG schema, rather than to a DTD or W3C XML Schema:

```
<?xml version="1.0" encoding="UTF-8"?>
<?xml-model href="urn:oasis:names:tc:dita:rng:topic.rng"?>
<topic id="MyTopic">
...
</topic>
```

The `<?xml-model?>` processing-instruction used in the above example is the standard way to associate a document to a RELAX NG schema. See [“Associating Schemas with XML documents 1.0”](#).

The DTDToSchema facility

The **DTDToSchema** facility can be used to “upgrade” your documents conforming to a DITA 1.3 DTD to the equivalent DITA 1.3 W3C XML Schema or RELAX NG schema. Command-line example showing how to invoke the **DTDToSchema** facility:

```
$ java -cp ditac_install_dir/lib/ditac.jar com.xmlmind.ditac.tool.DTDToSchema-
-rng MyTopic.dita
```

Before invoking the **DTDToSchema** facility, `MyTopic.dita` contained:

```
<?xml version="1.0" encoding="UTF-8"?>
<!DOCTYPE topic PUBLIC "-//OASIS//DTD DITA Topic//EN" "topic.dtd">
```

```
<topic id="MyTopic">
...
</topic>
```

After invoking the **DTDTToSchema** facility, `MyTopic.dita` contains:

```
<?xml version="1.0" encoding="UTF-8"?>
<?xml-model href="urn:oasis:names:tc:dita:rng:topic.rng"?>
<topic id="MyTopic">
...
</topic>
```

The **DTDTToSchema** facility is auto-documented:

```
$ java -cp ditac_install_dir/lib/ditac.jar com.xmlmind.ditac.tool.DTDTToSchema
```

```
Usage: java -cp ditac.jar com.xmlmind.ditac.tool.DTDTToSchema
       -rng|-xsd [ in_dita_file|in_dir_containing_dita_files ]+
```

"Upgrades" specified DITA documents conforming to a standard DITA 1.3 DTD to the corresponding W3C XML schema or RELAX NG schema.

Processes files or directories. Files are modified in place. Directories are recursively processed. All the '.ditamap', '.dita' and '.ditaval' files found in specified directories are processed.

Options:

```
-rng Upgrade to RELAX NG schema.
-xsd Upgrade to W3C XML schema.
```

Related information

- [Appendix C. Limitations and implementation specificities](#)

Appendix B. Lightweight DITA support

XMLmind DITA Converter fully supports [Lightweight DITA](#) (AKA LwDITA) support, whether [XDITA](#) (very small subset of DITA XML, plus new `<audio>` and `<video>` elements), [HDITA](#) (topics and maps written in  [HTML5](#)) or [MDITA](#) Extended Profile (topics and maps written in  [Markdown](#)).

XMLmind DITA Converter can of course process DITA documents comprising a mix of XDITA, HDITA, MDITA and (full) DITA topics and maps.

You'll find in the following sections some templates to start writing topics and maps in XDITA, HDITA and MDITA. You'll also find the list of HDITA and MDITA implementation specificities and limitations.

1. XDITA support

XMLmind DITA Converter fully supports [XDITA](#), which is basically a very small subset of DITA XML, plus [new audio and video elements](#).

Template of an XDITA topic (`lwdita_templates/xdita_topic.dita`):

```
<?xml version="1.0" encoding="UTF-8"?>
<!DOCTYPE topic PUBLIC "-//OASIS//DTD LIGHTWEIGHT DITA Topic//EN"
"lw-topic.dtd">
<topic id="???">
  <title></title>
  <shortdesc></shortdesc>
  <body>
    <p></p>
  </body>
</topic>
```

Template of an XDITA map (`lwdita_templates/xdita_map.dita`):

```
<?xml version="1.0" encoding="UTF-8"?>
<!DOCTYPE map PUBLIC "-//OASIS//DTD LIGHTWEIGHT DITA Map//EN"
"lw-map.dtd">
<map>
  <topicmeta>
    <navtitle></navtitle>
  </topicmeta>
  <topicref href="???">
    <topicref href="???" />
  </topicref>
  <topicref href="???" />
</map>
```

2. HDITA support

XMLmind DITA Converter fully supports [HDITA](#), which specifies how to write DITA topics and maps in [HTML5](#).



Important

Only *XHTML5*, that is, the XML syntax of HTML5, is supported. Plain HTML5 is *not* supported.

In practice, this means that all tags must be closed (e.g. `<img/>` and not `<img>`), all attributes must have a quoted value (e.g. `controls=""` and not `controls`) and that elements like `head` and `body` may not be omitted.

Template of an HDITA topic (`lwdita_templates/hdita_topic.html`):

```
<!DOCTYPE html>
<html xmlns="http://www.w3.org/1999/xhtml">
  <head>
    <meta charset="UTF-8"/>
    <title>Topic title here</title>
  </head>
  <body>
    <article id="???">
      <h1>Topic title here</h1>
      <p>Short description here.</p>
      <p>Topic body starts here.</p>
    </article>
  </body>
</html>
```

Template of an HDITA map (`lwdita_templates/hdita_map.html`):

```
<!DOCTYPE html>
<html xmlns="http://www.w3.org/1999/xhtml">
  <head>
    <meta charset="UTF-8"/>
    <title>Map title here</title>
  </head>
  <body>
    <nav>
      <h1>Map title here</h1>
      <ul>
        <li><p><a href="???"></a></p>
          <ul>
            <li><p><a href="???"></a></p></li>
            <li><p><a href="???"></a></p></li>
          </ul>
        </li>
        <li><p><a href="???"></a></p></li>
      </ul>
    </nav>
  </body>
</html>
```

Implementation specificities

- Adding attribute `data-class="concept"` to the top-level `article` element may be used to generate a DITA concept rather than a DITA topic.
- A footnote may be represented by `<div data-class="fn">`, in addition to `<span data-class="fn">`.

A footnote reference may be represented by `<a href="#FOOTNOTE_ID"></a>`.

- An internal link may be specified as `<a href="#TARGET_ID">`. Notice that there is no need to specify, like in DITA XML, `<a href="#./TARGET_ID">` or `<a href="#TOPIC_ID/TARGET_ID">`.
- Only the meta elements having the following names are translated to their DITA equivalent (that is, elements contained in the prolog of a DITA topic or the `topicmeta` of a DITA map):
 - audience
 - author
 - category
 - created or `dcterms.created` (maps to `<critdates>/<created>`)
 - keyword (maps to `<keywords>/<keyword>`)
 - permissions
 - publisher or `dcterms.publisher`
 - resourceid
 - revised or `dcterms.modified` (maps to `<critdates>/<revised>`)
 - source

A meta element having any other name is translated to DITA element `data`.

- While most HTML5 elements are faithfully translated to their DITA equivalent,
 - some elements (`br`, `hr`, `iframe`, `script`, etc) are simply ignored;
 - some other elements are translated to a DITA `ph` or `div` having an `outputclass` attribute reflecting their HTML5 origin.

Example 1: element `small` is translated to DITA `<ph outputclass="role-small">`.

Example 2: an `h1` element other than the very first one (specifying the title of the topic) is translated to DITA `<div outputclass="role-h1">`.

Example 3: nested sections are translated to DITA `<div outputclass="role-section">`.

Limitations

- Only *XHTML5*, that is, the XML syntax of HTML5, is supported. Plain HTML5 is *not* supported.
- Using attribute `rowspan` in `td` or `th` elements will generally cause an incorrect DITA table to be generated.

3. MDITA support

XMLmind DITA Converter fully supports **MDITA**, which specifies how to write DITA topics and maps in **Markdown**.

Template of an MDITA topic [lwdita_templates/mdita_topic.md](#):

```
---
id: ???
---

# Topic title here

Short description here.

Topic body starts here.
```

Template of an MDITA map [lwdita_templates/mdita_map.md](#):

```
# Map title here {.map}

- [???](???)
- [???](???)
- [???](???)
- [???](???)
```

Notice the `{.map}` class attribute added to the title of the map. Without it, the above template would be translated to a DITA topic.

Implementation specificities

- The encoding of an MDITA file is, by default, the system encoding (e.g. window-1252 on a Western PC).

If you want to explicitly specify the encoding of an MDITA file, please save your file with a UTF-8 or UTF-16 BOM (Byte Order Mark) or add an *encoding directive* inside a comment anywhere at the beginning of your file. Example:

```
<!-- -*- coding: iso-8859-1 -*- -->

Heading
=====

## Sub-heading

Paragraphs are separated
by a blank line.
```

The above example should work fine because ditac understands the [GNU Emacs file variable](#) called `coding`.

- Adding a `{.concept}` class attribute to the title of an MDITA topic may be used to generate a DITA concept rather than a DITA topic.
- Out of the box, ditac supports the so-called *Extended Profile*.

This Extended Profile may be customized by the means of `-p load.mdita.XXX parameters`. These `load.mdita.XXX` parameters are documented [below](#).

Limitations

- Without a `{.map}` class attribute added to the title of an MDITA map, this map is confused with a topic.

load.mdita.XXX parameters

Parameter `-p load.mdita.extended-profile true` is implicitly passed to `ditac`. This parameter is simply a shorthand for:

```
-p load.mdita.abbreviation true
-p load.mdita.admonition true
-p load.mdita.attributes true
-p load.mdita.definition true
-p load.mdita.footnotes true
-p load.mdita.gfm-strikethrough true
-p load.mdita.ins true
-p load.mdita.superscript true
-p load.mdita.tables true
-p load.mdita.typographic true
-p load.mdita.yaml-front-matter true
```

where `abbreviation`, `admonition`, `attributes`, etc, are all *Markdown extensions*, documented in [Markdown extensions](#).

If for example, you don't like the stock Extended Profile and prefer to use a simpler one, plus the `autolink` Markdown extension⁽¹⁴⁾, then pass:

```
-p load.mdita.core-profile true
-p load.mdita.autolink true
```

to `ditac`.

Parameter `-p load.mdita.core-profile true` is simply a shorthand for:

```
-p load.mdita.gfm-strikethrough true
-p load.mdita.superscript true
-p load.mdita.tables true
-p load.mdita.yaml-front-matter true
```

3.1. Markdown extensions

Abbreviations

Converts plain text abbreviations (e.g. IBM) to `<abbr>` elements.

This Markdown syntax extension, which is part of the MDITA Extended Profile, is enabled by default. In order to disable it, pass parameter `-p load.mdita.abbreviation false` to `ditac`.

Example:

```
The HTML specification is maintained by the W3C.
```

⁽¹⁴⁾ Turns plain text URLs and email addresses into `<xref href="...">` elements.

```
*[HTML]: Hyper Text Markup Language
*[W3C]: World Wide Web Consortium
```

is converted to:

```
<p>The <keyword>HTML</keyword> specification is maintained
by the <keyword>W3C</keyword>.</p>
```

which is rendered as:

The HTML specification is maintained by the W3C.

Admonitions

Syntax for creating admonitions such as notes, tips, warnings, etc.

This Markdown syntax extension, which is part of the MDITA Extended Profile, is enabled by default. In order to disable it, pass parameter `-p load.mditad.admonition false` to `ditac`.

After the `!!!` tag, the admonition type must be one of "note", "attention", "caution", "danger", "fastpath", "important", "notice", "remember", "restriction", "tip", "trouble", "warning".

A note example not having a title:

```
!!! note ""
    Support is limited to bug reports.
```

is converted to:

```
<note>
  <p>Support is limited to bug reports.</p>
</note>
```

which is rendered as:



Note

Support is limited to bug reports.

A tip example having a title:

```
!!! tip "How do you do a hard reboot on an iPad?"
    Press and hold both the Home and Power buttons
    until your iPad® reboots.

    You can release both buttons when you see Apple® logo.
```

is converted to:

```
<note type="tip">
  <div outputclass="note-title role-h4">How do you
do a hard reboot on an iPad?</div>

  <p>Press and hold both the <b>Home</b> and <b>Power</b>
```

```

    buttons until your iPad® reboots.</p>

    <p>You can release both buttons when you see
    Apple® logo.</p>
  </note>

```

which is rendered as:



Tip

How do you do a hard reboot on an iPad?

Press and hold both the **Home** and **Power** buttons until your iPad® reboots.

You can release both buttons when you see Apple® logo.

Attributes

Syntax for adding attributes to the generated HTML elements:

```

attributes -> '{' attribute_spec ( S attribute_spec)* '}'

attribute_spec ->   name=value
                   | name='value'
                   | name="value"
                   | #id
                   | .class

```



Remember

An easy rule to remember

If an `{...}` specification is separated by space characters from some plain text (e.g. some plain text `{...}`) then the attributes are added to the parent element of the text.

This Markdown syntax extension, which is part of the MDITA Extended Profile, is enabled by default. In order to disable it, pass parameter `-p load.mdita.attributes false` to `ditac`.

Example:

```

The *circumference { .first-term }* is the length of one circuit along the
circle, or the distance around the circle. {#circumference}

```

is converted to:

```

<p id="circumference">The <i outputclass="first-term">circumference</i>
is the length of one circuit along the circle, or the distance around
the circle.</p>

```

which is rendered as:

The *circumference* is the length of one circuit along the circle, or the distance around the circle.

**Attention****Pitfall**

By default, heading IDs are not “rendered” in HTML (which is somewhat counterintuitive). You must pass `-p load.m dita.renderer.RENDER_HEADER_ID true` to `ditac` get them “rendered”.

Automatic links

Turns plain text URLs and email addresses into `<a href="...">` elements.

This Markdown syntax extension is disabled by default. In order to enable it, pass parameter `-p load.m dita.autolink true` to `ditac`.

Example:

```
Please send your bug reports to support@xmlmind.com, a public,
moderated, mailing list. More information in https://xmlmind.com/.
```

is converted to:

```
<p>Please send your bug reports to <xref
href="mailto:support@xmlmind.com">support@xmlmind.com</xref>,
a public, moderated, mailing list. More information in <xref
href="https://xmlmind.com/">https://xmlmind.com/</xref>.</p>
```

which is rendered as:

Please send your bug reports to support@xmlmind.com, a public, moderated, mailing list. More information in [http://www.xmlmind.com/](https://www.xmlmind.com/).

Definition lists

Syntax for creating definition lists, that is `<dl>`, `<dt>` and `<dd>` elements.

This Markdown syntax extension, which is part of the MDITA Extended Profile, is enabled by default. In order to disable it, pass parameter `-p load.m dita.definition false` to `ditac`.

Example:

Glossary:

LED

: Light emitting diode.

ABS

: Antilock braking system.

ESC

ESP

: Electronic stability control, also known as Electronic Stability Program.

: On motorcycles, ESC/ESP is called **Traction Control**.

```
> Ducati was one of the first to introduce a true competition-level
> traction control system (**DTC**) on a production motorcycle.
```

```
EBA
: Emergency brake assist.
```

is converted to:

```
<p>Glossary:</p>
<dl>
  <dlentry>
    <dt>LED</dt>
    <dd>
      <p>Light emitting diode.</p>
    </dd>
  </dlentry>
  <dlentry>
    <dt>ABS</dt>
    <dd>
      <p>Antilock braking system.</p>
    </dd>
  </dlentry>
  <dlentry>
    <dt>ESC</dt>
    <dt>ESP</dt>
    <dd>
      <p>Electronic stability control, also known as
      Electronic Stability Program.</p>
    </dd>
    <dd>
      <p>On motorcycles, ESC/ESP is called <i>Traction Control</i>.</p>
      <lq>
        <p>Ducati was one of the first to introduce a
        true competition-level traction control system
        (<b>DTC</b>) on a production motorcycle.</p>
      </lq>
    </dd>
  </dlentry>
  <dlentry>
    <dt>EBA</dt>
    <dd>
      <p>Emergency brake assist.</p>
    </dd>
  </dlentry>
</dl>
```

which is rendered as:

Glossary:

LED

Light emitting diode.

ABS

Antilock braking system.

ESC**ESP**

Electronic stability control, also known as Electronic Stability Program.

On motorcycles, ESC/ESP is called *Traction Control*.

Ducati was one of the first to introduce a true competition-level traction control system (**DTC**) on a production motorcycle.

EBA

Emergency brake assist.

**Remember**

Remember that:

- The leading ":" character of a definition must be followed by one or more space characters.
- Terms must be separated from the previous definition by a blank line.
- A blank line is not allowed between two consecutive terms.
- A blank line is allowed before a definition.

Footnotes

Syntax for creating footnotes and footnote references.

This Markdown syntax extension, which is part of the MDITA Extended Profile, is enabled by default. In order to disable it, pass parameter `-p load.mdita.footnotes false` to ditac.

Example:

The differences between the programming languages C++^[^1] and Java can be traced to their heritage.

^[^1]: The C++ Programming Language by Bjarne Stroustrup.

C++^[^1] was designed for systems and applications programming, extending the procedural programming language C^[^2].

^[^2]: The C Programming Language by Brian Kernighan and Dennis Ritchie.

Originally published in 1978.

is converted to:

```
<p>The differences between the programming languages
C++<xref href="#/_FN1" type="fn"/> and Java can
be traced to their heritage.</p>
```

```

<div>
  <fn id="__FN1">The C++ Programming Language by
    Bjarne Stroustrup.</fn>
</div>

<p>C++<xref href="#./__FN1" type="fn"/> was designed
for systems and applications programming, extending
the procedural programming
language C<xref href="#./__FN2" type="fn"/>.</p>

<div>
  <fn id="__FN2">The C Programming Language by
    Brian Kernighan and Dennis Ritchie.
  <p>Originally published in 1978.</p> </fn>
</div>

```

which is rendered as:

The differences between the programming languages C++⁽¹⁵⁾ and Java can be traced to their heritage.

C++⁽¹⁵⁾ was designed for systems and applications programming, extending the procedural programming language C⁽¹⁶⁾.

Strikethrough and subscript

Converts

- tagged text "~~something deleted~~" to `<del>something deleted</del>`, which is rendered as: something deleted
- tagged text "_{a subscript}" to `<sub>a subscript</sub>`, which is rendered as: a subscript

This Markdown syntax extension, which is part of the MDITA Core Profile and the MDITA Extended Profile, is enabled by default. In order to disable it, pass parameter `-p load.mdita.gfm-strikethrough false` to ditac.

Ins

Converts tagged text "something new" to `<ins>something new</ins>`, which is rendered as: something new

This Markdown syntax extension, which is part of the MDITA Extended Profile, is enabled by default. In order to disable it, pass parameter `-p load.mdita.ins false` to ditac.

Superscript

Converts tagged text "^{a superscript}" to `<sup>a superscript</sup>`, which is rendered as: ^a superscript

⁽¹⁵⁾The C++ Programming Language by Bjarne Stroustrup.

⁽¹⁶⁾The C Programming Language by Brian Kernighan and Dennis Ritchie.

Originally published in 1978.

This Markdown syntax extension, which is part of the MDITA Extended Profile, is enabled by default. In order to disable it, pass parameter `-p load.mdita.superscript false` to ditac.

Media tags

Converts prefixed links to audio and video HTML5 elements.

- `!A[Text](links)` - audio. *Links* is one or more links separated by character “|”.
- `!V[Text](links)` - video.

Audio example:

```
Audio example: !A[Sample audio](media/audio.mp3|media/audio.wav).
```

is converted to:

```
<p>Audio example: <audio>
  <desc>Sample audio</desc>
  <media-controls value="true"/>
  <media-source value="media/audio.mp3"/>
  <media-source value="media/audio.wav"/>
</audio>.</p>
```

Video example:

```
Video example: !V[Sample video](media/video.mp4).
```

is converted to:

```
<p>Video example: <video>
  <desc>Sample video</desc>
  <media-controls value="true"/>
  <media-source value="media/video.mp4"/>
</video>.</p>
```

This Markdown syntax extension is disabled by default. In order to enable it, pass parameter `-p load.mdita.media-tags true` to ditac.



Restriction

This extension cannot be used if you are authoring a DITA document. It will only work if you are authoring an **LwDITA** document. Only LwDITA supports the `<audio>` and `<video>` elements.

Tables

Converts pipe “|” delimited text to `<table>` elements.

This Markdown syntax extension, which is part of the MDITA Core Profile and the MDITA Extended Profile, is enabled by default. In order to disable it, pass parameter `-p load.mdita.tables false` to ditac.

Simple table example:

```
| Header 1 | Header 2 | Header 3 |
```

```
| ----- | ----- | ----- |
| Cell 1,1 | Cell 1,2 | Cell 1,3 |
| Cell 2,1 | Cell 2,2 | Cell 2,3 |
```

is converted to:

```
<table >
  <tgroup cols="3">
    <thead>
      <row valign="middle">
        <entry align="center">Header 1</entry>
        <entry align="center">Header 2</entry>
        <entry align="center">Header 3</entry>
      </row>
    </thead>
    <tbody>
      <row valign="middle">
        <entry>Cell 1,1</entry>
        <entry>Cell 1,2</entry>
        <entry>Cell 1,3</entry>
      </row>
      <row valign="middle">
        <entry>Cell 2,1</entry>
        <entry>Cell 2,2</entry>
        <entry>Cell 2,3</entry>
      </row>
    </tbody>
  </tgroup>
</table>
```

which is rendered as:

Header 1	Header 2	Header 3
Cell 1,1	Cell 1,2	Cell 1,3
Cell 2,1	Cell 2,2	Cell 2,3

Table example having centered and right-aligned columns:

```
| Header 1 | Header 2          | Table Header 3 |
| ----- | :-----:         | -----:      |
| Cell 1,1 | Table cell 1,2    | Cell 1,3       |
| Cell 2,1 | Cell 2,2          | Cell 2,3       |
```

is converted to:

```
<table>
  <tgroup cols="3">
    <thead>
      <row valign="middle">
        <entry align="center">Header 1</entry>
        <entry align="center">Header 2</entry>
        <entry align="right">Table Header
          3</entry>
```

```

    </row>
  </thead>
  <tbody>
    <row valign="middle">
      <entry>Cell 1,1</entry>
      <entry align="center">Table cell
        1,2</entry>
      <entry align="right">Cell 1,3</entry>
    </row>
    <row valign="middle">
      <entry>Cell 2,1</entry>
      <entry align="center">Cell 2,2</entry>
      <entry align="right">Cell 2,3</entry>
    </row>
  </tbody>
</tgroup>
</table>

```

which is rendered as:

Header 1	Header 2	Table Header 3
Cell 1,1	Table cell 1,2	Cell 1,3
Cell 2,1	Cell 2,2	Cell 2,3

Table example having cells spanning several columns and a caption:

```

| Header 1 | Header 2 | Header 3 |
| ----- | ----- | ----- |
| Cell 1,1 + 1,2      | Cell 1,3 |
| Cell 2,1 + 2,2 + 2,3      | ||
| Cell 3,1 | Cell 3,2 | Cell 3,3 |
[Table caption here]

```

is converted to:

```

<table>
  <title>Table caption here</title>
  <tgroup cols="3">
    <colspec colname="c1" rowheader="headers"/>
    <colspec colname="c2" rowheader="headers"/>
    <colspec colname="c3" rowheader="headers"/>
    <thead>
      <row valign="middle">
        <entry align="center">Header 1</entry>
        <entry align="center">Header 2</entry>
        <entry align="center">Header 3</entry>
      </row>
    </thead>
    <tbody>
      <row valign="middle">
        <entry nameend="c2" namest="c1">Cell 1,1
          + 1,2</entry>
        <entry>Cell 1,3</entry>
      </row>
    </tbody>
  </tgroup>
</table>

```

```

</row>
<row valign="middle">
  <entry nameend="c3" namest="c1">Cell 2,1
    + 2,2 + 2,3</entry>
</row>
<row valign="middle">
  <entry>Cell 3,1</entry>
  <entry>Cell 3,2</entry>
  <entry>Cell 3,3</entry>
</row>
</tbody>
</tgroup>
</table>

```

which is rendered as:

Table B-1. Table caption here

Header 1	Header 2	Header 3
Cell 1,1 + 1,2		Cell 1,3
Cell 2,1 + 2,2 + 2,3		
Cell 3,1	Cell 3,2	Cell 3,3

Typographic characters

Converts

- `"'` to apostrophe `’`; , which is rendered as in word: "don't"
- `"..."` and `". . ."` to ellipsis `…`; , which are both rendered as: ...
- `"-"` to en dash `–`; , which is rendered as: –
- `"--"` to em dash `—`; , which is rendered as: —
- single quoted `'some text'` to `‘`some text`’`; , which is rendered as: ‘some text’
- double quoted `"some text"` to `“`some text`”`; , which is rendered as: “some text”
- double angle quoted `<<some text>>` to `«`some text`»`; , which is rendered as: «some text»

This Markdown syntax extension, which is part of the MDITA Extended Profile, is enabled by default. In order to disable it, pass parameter `-p load.mdita.typographic false` to `ditac`.

If you don't want some of the above plain text sequences to be processed, specify:

-p load.mdita.typographic.ENABLE_QUOTES false

Do not process single quotes, double quotes, double angle quotes.

-p load.mdita.typographic.ENABLE_SMARTS false

Do not process `"'`, `"..."`, `". . ."`, `"-"`, `"--"`.

YAML front matter

Syntax for adding metadata to the generated DITA topic or map, that is, for populating the `<prolog>` element of a DITA topic and the `<topicmeta>` element of a DITA map.

These metadata are specified by key/value pairs written using a subset of the [YAML](http://yaml.org/) (see also <http://yaml.org/>) syntax.

Supported metadata are:

- audience
- author
- category
- created (maps to <critdates>/<created>)
- keyword (maps to <keywords>/<keyword>)
- permissions
- publisher
- resourceid
- revised (maps to <critdates>/<revised>)
- source

Any other metadata is translated to DITA element <data>.

This Markdown syntax extension, which is part of the MDITA Core Profile and the MDITA Extended Profile, is enabled by default. In order to disable it, pass parameter `-p load.mdita.yaml-front-matter false` to `ditac`.

Example:

```
---
author:
  - Brian W. Kernighan
  - Dennis Ritchie
publisher: Prentice Hall
created: 1978/01/01
revised: 1988/01/01
---
```

is converted to:

```
<prolog>
  <author>Brian W. Kernighan</author>
  <author>Dennis Ritchie</author>
  <publisher>Prentice Hall</publisher>
  <critdates>
    <created date="1978/01/01"/>
    <revised modified="1988/01/01"/>
  </critdates>
</prolog>
```

Other extensions

The following Markdown syntax extensions are also supported:

- anchorlink
- aside

- emoji
- enumerated-reference
- gfm-issues
- gfm-tasklist
- gfm-users
- toc
- wikilink
- youtube-embedded

All the above extensions are disabled by default. In order to enable an extension, pass parameter `-p load.m dita.EXTENSION_NAME true` to ditac. For example: `-p load.m dita.emoji true`

Any extension listed in this section may be parameterized by passing parameter `-p load.m dita.EXTENSION_NAME.PARAMETER_NAME PARAMETER_VALUE(17)` to ditac. Examples:

- `-p load.m dita.emoji.ATTR_IMAGE_SIZE 16`
- `-p load.m dita.emoji.ATTR_ALIGN ""`
- `-p load.m dita.emoji.USE_IMAGE_TYPE IMAGE_ONLY`
- `-p load.m dita.emoji.USE_SHORTCUT_TYPE ANY_GITHUB_PREFERRED`

More generally, the Markdown parser (pseudo *EXTENSION_NAME* is "parser") and the HTML renderer (pseudo *EXTENSION_NAME* is "renderer") may also be parameterized this way. For example, automatically generate an ID for all headings not already having an ID **and** “render” all heading IDs in HTML⁽¹⁸⁾:

```
-p load.m dita.renderer.GENERATE_HEADER_ID true
-p load.m dita.renderer.RENDER_HEADER_ID true
```

More information about extensions and their parameters in [Extensions](#) ([flexmark-java](#) is the software component used by ditac to parse Markdown and convert it to HTML).

⁽¹⁷⁾The only types supported for *PARAMETER_VALUE* are: string, boolean (`true` or `false`), integer and any enumerated type.

⁽¹⁸⁾By default, heading IDs are not “rendered” in HTML, which is somewhat counterintuitive.

Appendix C. Limitations and implementation specificities

Conversion to XHTML and XSL-FO

- The following elements are ignored:
 - the `<syntaxdiagram>` element and all its descendant elements;
 - `<ux-window>`;
 - `<sort-as>`.
- Layout of `<simplatable>` elements:
 - Attribute `@frame` is ignored.
 - Conversion to XHTML:
 - Attribute `@expanse` is partially supported. Its value is considered to always be 100%.
 - Conversion to XSL-FO:
 - Attribute `@expanse` is ignored. The width of a `<simplatable>` is always 100% and thus, you cannot center a `<simplatable>` using the `center` parameter.
- Layout of (CALS) `<table>` element:
 - Attribute `<entry>/@rotate` is not supported.
 - Conversion to XHTML:
 - Attribute `<table>/@orient="land"` (landscape table) is not supported.
 - Attribute `@pgwide` is partially supported. Its value is considered to always be 100%.
 - Something like `colwidth="2*+3pt"` is treated as if it were `colwidth="2*"`. Moreover, because no Web browser seems to support relative lengths, a relative length is approximated to a percentage.
 - Conversion to XSL-FO:
 - Attribute `<table>/@orient="land"` (landscape table) is supported. However, except when the XSL-FO processor being invoked by ditac is [XMLmind XSL-FO Converter v6.2+](#), the landscape table must have few enough rows to fit onto one page. When this is not the case, the last rows of the landscape table will simply not appear in the output.
 - Attribute `@pgwide` is ignored. The width of a `<table>` is always 100% and thus, you cannot center a `<table>` using the `center` parameter.
- The qualified ID of a descendant element of a topic is transformed as follows: *topicID/descendantID* becomes *topicID__descendantID* in the generated content. (The separator string being used comprises two underscore characters.)

Example: let's suppose a topic having "parameters" as its `@id` attribute, containing a table having "default_values" as its `@id` attribute, has been converted to HTML. The generated HTML file which contains the topic is called `userguide.html`.

- URL `"userguide.html#parameters"` allows to address the topic.
- URL `"userguide.html#parameters__default_values"` allows to address the table.

Booklists

- Contents corresponding to the following empty `<bookmap>` elements: `<toc>`, `<tablelist>`, `<figurelist>`, `<indexlist>` can be automatically generated by ditac.
- Ditac supports `<examplelist>` and `<equationlist>` in addition to `<toc>`, `<tablelist>`, `<figurelist>`, `<indexlist>`.
- Contents corresponding to the following empty `<bookmap>` elements: `<trademarklist>`, `<abbrevlist>`, `<bibliolist>`, `<glossarylist>` *cannot* be automatically generated by ditac.
- Entries automatically generated by ditac for `<toc>`, `<tablelist>`, `<figurelist>`, `<examplelist>`, `<equationlist>` and `<indexlist>` only contain plain text. For example, if a topic title is "`<title>The JavaTM <b>Spring</b> framework</title>`", then the corresponding TOC entry contains "The JavaTM Spring framework".
- About the automatically generated `<indexlist>`:
 - Specifying an `<indexterm>` element in the `<topicmeta>/<keywords>` element of a `<topicref>` element is equivalent to specifying it in the `<prolog>/<metadata>/<keywords>` element of the corresponding topic. Any other `<indexterm>` element found in a map is ignored.
 - In a topic, the implicit end of an index range is always after the last child of the topic, not including nested topics.
 - Overlapping index ranges are not supported.
 - The markup possibly contained in an `<indexterm>` (`<option>`, `<parmname>`, `<apiname>`, etc) is ignored.
 - Because we consider this feature to be truly useful, we'll generate page references and ``see also'' redirections even for non-leaf index terms. No warnings will be reported in this case. If you don't like this specificity, simply do not author such `<indexterm>` elements.
 - Unless specified using the `-lang` command-line option, the language of the document is taken from the `@xml:lang` attribute of the root element of the topic map. If there is no such attribute, the language defaults to "en". Knowing the language of the document is required to be able to generate localized text (e.g. "Kapitel") and to sort and group the index entries.

Keyref processing

- Matching element content taken from a key definition is limited to the following cases:
 - A `<link>` element gets its `<linktext>` child from `key_definition/topicmeta/linktext` and its `<desc>` child from `key_definition/topicmeta/shortdesc`.
 - An `<xref>` element gets its contents from `key_definition/topicmeta/linktext`.
 - Elements `<ph>`, `<cite>`, `<keyword>`, `<dt>` and `<term>` all get their content from `key_definition/topicmeta/keywords/keyword`, if any. Otherwise the contents of `key_definition/topicmeta/linktext` is used as a fallback.
- Key-based, cross-deliverable addressing is not implemented.
- Topics which are not directly or indirectly referenced by the root map are automatically added to the root key scope. Such topics typically contain common content which is included by other topics using `@conref`.

If you don't want this to happen, please explicitly reference such common content topics in your maps and mark these references as being resource-only. Example:

```
<topigroup keyscope="MyKeyscope">
```

```
<topicref href="commonContent.dita" processing-role="resource-only"/>
```

Transclusion

- During a conref transclusion, ditac does not check the compatibility of the domains of the referencing document with the domains of the referenced document. This can be changed by defining system property DITAC_CHECK_DOMAINS (that is, adding -DDITAC_CHECK_DOMAINS=1 to the bin/ditac shell script or to bin/ditac.bat). However, the verifications performed by ditac are almost certainly not conforming as we have not really understood the spec.
- Transclusion does not implement automatic generalization. For example, transcluding `<li conref="foo.dita#foo/item3"/>` will report a fatal error if "foo/item3" is a `<step>` element.

A `<step>` element is a specialization of a `<li>` element. Some DITA processors are capable of automatically converting a `<step>` element to an `<li>` element. This is not the case of ditac.

- By default, the character encoding of the text file included using a [<coderef> element](#) is automatically determined by ditac (e.g. by examining the BOM or `<?xml encoding="XXX"?>`). You may specify this character encoding explicitly by adding a `format="text; charset=XXX"` attribute to the `<coderef>` element. Example: `<coderef format="text; charset=US-ASCII" href="../../src/sieve.cpp"/>`.

Cascading of attributes and metadata

- Filtering and flagging may be performed using any attribute. However only the following attributes: `<audience>`, `<platform>`, `<product>`, `<otherprops>`, `<props>`, specializations of attributes `<props>` and `<rev>` properly cascade with a map, within the `<related-links>` element of a topic and from a `<topicref>` element to the referenced `<topic>` element.
- Both attribute (e.g. `@audience`) and element (e.g. `<audience>`) metadata are copied from a `<topicref>` element to the referenced `<topic>` element.
- Unless `topicref/topicmeta/@lockmeta=no`, `topicref/topicmeta/searchtitle` supplements or overrides `topic/titlealts/searchtitle`.
- In the following case, `<topicref href="foo.dita"/>`, the `<topicref>` metadata is copied only to the first topic found in `foo.dita`. An alternative would be to copy metadata to all topics found in `foo.dita`.

Subject scheme maps

- XMLmind DITA Converter supports all the features documented in ["2.2.3 Subject scheme maps and their usage"](#) when these features are related to attribute values.
- Only the following useful subset of the grammar of subject scheme maps is supported by ditac. Any other [subject scheme element](#) is silently ignored:

```
<subjectScheme>
  Content: [ subjectdef | enumerationdef | schemeref ]*
</subjectScheme>

<subjectdef
  keys = name of a set of attribute values OR an attribute value
  OR
  keyref = name of a set of attribute values OR an attribute value
  navtitle = description of this subjectdef
```

```

>
  Content: [ <topicmeta>
            <navtitle>description of this subjectdef</navtitle>
          </topicmeta> ]?
        [ subjectdef ]*
</subjectdef>

<enumerationdef>
  Content: [ elementdef ]*
          attributedef
          <subjectdef
            keyref = name of a set of attribute values
                    (keyref absent means:
                     don't use this attribute)
          />
</enumerationdef>

<elementdef
  name = element qualified name
/>

<attributedef
  name = attribute qualified name
/>

<schemeref
  href = location of another subject scheme map
/>

```

- All the subject scheme maps referenced in the map⁽¹⁹⁾ to be converted and in all its submaps are loaded in turn and their contents are merged as if a single subject scheme map was specified at the very beginning of the main map.
- It's also possible to specify which subject scheme map to use by the means of the **-attrvalues** and **-defaultattrvalues** command-line options.
- **Attribute groups** are fully supported both for attribute value validation and when filtering and flagging. Example, some of the values declared for attribute `@platform`:

```

<subjectdef keys="macos"/>
<subjectdef keys="linux">
  <subjectdef keys="redhat"/>
  <subjectdef keys="ubuntu"/>
</subjectdef>

```

A validation error will be reported for attribute `platform="linux(redhat debian)"` because "debian" has not been declared. A validation error will be reported for attribute `platform="macos(redhat)"` because "redhat" is not a kind of "macos".

⁽¹⁹⁾Typically using `<mapref type="scheme" href="my_subject_scheme_map.ditamap"/>`.

Conditional processing

- Conditional processing is also applied to the information (e.g. <title>, <metadata>) contained in a map. However, only the exclude action will work. The flag action does not work in this context.
- Any attribute (that is, not only @audience, @platform, @product, @rev, @otherprops, @deliveryTarget and attributes specialized from @props) may be used to filter or flag an element. For example, the @status attribute may be used to highlight changes. See [below](#).
- Subject scheme maps, which should be used to validate attribute values and also to implement smarter conditional processing, are currently ignored.
- If a map directly contains multiple <ditavalref> elements, all <ditavalref> elements but the first one are ignored. When this is the case, a warning is reported, though.
- The externally specified DITaval file is combined with the <ditavalref> element, if any, which is a direct child of a map.
- <ditavalref> [error conditions](#) are not detected.
- In a DITaval file, `action="passthrough"` is not supported.

Flagging contents

- Only the following elements (and, of course, their specializations) can be flagged *without restrictions*: <topic>, <p>, <lq>, <note>, <dl>, , , <sl>, <pre>, <lines>, <fig>, <object>, <table>, <simplatable>, <section>, <example>, <ph>, <term>, <xref>, <cite>, <q>, <boolean>, <state>, <keyword>, <tm>, <image>, <foreign>.

Any other element (, <dlentry>, <step>, <stentry>, etc) is just given *some* of the colors and font styles, if any, specified by the flagging elements and attributes found in the .ditaval file.

- In a .ditaval file, attribute `style="double-underline"` is processed as if it were underline.
- In a .ditaval file, attribute `style="line-through"` is supported in addition to underline and overline.
- The @status attribute may be used to highlight changes. Example:

```
$ ditac -filter status.ditaval doc.pdf doc.ditamap
```

where file status.ditaval contains:

```
<val>
  <prop action="flag" att="status" bgcolor="#FFFF99" style="underline"
    val="new"/>

  <prop action="flag" att="status" bgcolor="#99FF99" val="changed"/>

  <prop action="flag" att="status" bgcolor="#FF7F7F" style="line-through"
    val="deleted"/>
</val>
```

and where doc.ditamap references a topic containing for example:

```
<p>A paragraph containing <ph status="new">new text</ph>,
<ph status="changed">changed text</ph>,
<ph status="deleted">deleted text</ph>.</p>
...
```

```

<p status="new">New paragraph.</p>
...
<ul status="changed">
  <li>First item in changed <tt>ul</tt>.</li>
  <li><p>Second item.</p>
    <p status="deleted">Deleted paragraph.</p></li>
  <li>Third item.</li>
</ul>

```

- In a .ditaval file, the value of the @changebar attribute of the <revprop> element, has the following syntax:

changebar -> prop [S ';' S prop]+

prop -> prop_name ':' S prop_value

The style properties supported there are:

Name	Value	Default	Description
color	<color>	The value of the color property.	See XSL 1.1 property change-bar-color.
offset	<length>	6pt	See XSL 1.1 property change-bar-offset.
placement	start end left right inside outside alternate	start	See XSL 1.1 property change-bar-placement.
style	<border-style>	solid	See XSL 1.1 property change-bar-style.
width	<border-width>	medium	See XSL 1.1 property change-bar-width.

Example:

```
$ ditac -filter changebar.ditaval doc.pdf doc.ditamap
```

where file changebar.ditaval contains:

```

<val>
  <revprop action="flag" val="2.1"
    changebar="style: double; width: 3px; placement: start;" ></revprop>
</val>

```

and where doc.ditamap references a topic containing for example:

```

...
<fig rev="2.1">
  <title>The logo of ACME corp.</title>
  <image href="acme_logo.png"/>
</fig>
...

```

- Change bars are implemented by the following processors: [Apache FOP](#), [RenderX XEP](#) and [Antenna House Formatter](#). For any other XSL-FO processor (e.g. [XMLmind XSL-FO Converter](#)) and also for all XHTML-based output formats (e.g. EPUB, Web Help), change bars are emulated using left or right borders. This emulation may give poor results when a change bar is added to a table.

Generating links

- Attribute `@collection-type`, whatever its value, is ignored inside the `<reltable>` element.
- Dita cannot generate “smart labels” for related links. The label is always “Related Links”. It could have been “Related Concepts”, “Related Reference” or even something determined using what is specified in the `<title>` child element of a `<relcolspec>` element.

Chunking

- The “to-navigation” chunk value is ignored.
- When the `@copy-to` attribute is used to specify an URI, the parent path part (e.g. “foo” in “foo/bar.htm”) and the extension part (e.g. “.htm” in “foo/bar.htm”) are ignored. Only the “root name” (e.g. “bar” in “foo/bar.htm”) is taken into account during the processing of the map.
- The default chunking policy is by-document.
- When the deliverable targets a print media, all chunk specifications are removed and a `chunk="to-content"` attribute is added to the root element of the map.

Other limitations and specificities

- `<topicref>` elements found inside a `<reltable>` do not “pull” the corresponding topics. In other words, a `<reltable>` cannot be used to add some content to a deliverable. With dita, a `<reltable>` is just used to create links between topics which are already part of the deliverable.
- There are several limitations and inconsistencies when working with files containing multiple topics and/or nested topics.

For example, let's suppose a map contains the following `<topicref>`s, where `multi.dita` contains multiple topics (first topic being `t1`, second topic being `t2`), each topic possibly containing nested topics.

```
<topicref href="multi.dita"/>
<topicref href="multi.dita"/>
<topicref href="multi.dita#t1"/>
<topicref href="multi.dita#t2"/>
```

- As expected, the first `<topicref>` pulls all the topics, including nested ones, contained in `multi.dita`. However parent, child, sibling, etc, related links will *not* be automatically generated for these topics.
- The second `<topicref>` pulls a copy of all the topics, including nested ones, contained in `multi.dita`. The third `<topicref>` pulls a copy of topic `t1` (excluding nested topics). The fourth `<topicref>` is *not* detected as pulling a copy of topic `t2`. Therefore the fourth `<topicref>` does nothing at all, as topic `t2` has already been pulled into the deliverable (by the first `<topicref>`).
- The following `<topicref>` elements are not treated differently from the others: `<topicset>`, `<topicsetref>`.
- The following `<bookmap>` elements: `<abbrevlist>`, `<amendments>`, `<appendices>`, `<appendix>`, `<bibliolist>`, `<bookabstract>`, `<booklist>`, `<chapter>`, `<colophon>`, `<dedica-`

tion>, <draftintro>, <figurelist>, <examplelist>, <equationlist>, <glossarylist>, <indexlist>, <notices>, <part>, <preface>, <tablelist>, <toc>, <trademarklist>, are considered to have an *implicit title* when

- they have no @href attribute,
- and they have no explicit title,
- and they contain one or more <topicref> (of any type) child elements.

For example:

```
<glossarylist>
  <topicref href="term1.dita"/>
  <topicref href="term2.dita"/>
  <topicref href="term3.dita"/>
</glossarylist>
```

is processed as if it was:

```
<glossarylist navtitle="Glossary">
  <topicref href="term1.dita"/>
  <topicref href="term2.dita"/>
  <topicref href="term3.dita"/>
</glossarylist>
```

- All attributes and elements — map/@anchorref, <anchorref>, <anchor>, <navref> — related to runtime integration of maps are ignored.
- Ditac reports a "*topicB*, href points outside processed topics" warning when *topicA* references *topicB* and *topicB* is not referenced in the map. In order to suppress this warning, add to the map a <topicref> having attribute toc="no" and pointing to *topicB*.
- Convenience element <glossref> cannot be used with ditac without setting some of its attributes. Example:

```
<glossref href="ONE.dita" keys="key_ONE"/>
```

is strictly equivalent to:

```
<topicref href="ONE.dita" keys="key_ONE" linking="none" print="no"
  toc="no" search="no"/>
```

Notice default attribute print="no". Therefore, when generating PDF, such <glossref> is discarded at a very early stage by ditac. The consequence is that each occurrence of <abbreviated-form keyref="key_ONE"/> will cause ditac to report a "cannot resolve keyref" warning. The workaround is to simply avoid using <glossref> and to stick to <topicref> with a @keys attribute.

Related information

- [Appendix A. About DITA support in XMLmind DITA Converter](#)

Appendix D. Translating the messages generated by ditac

About this task

The messages generated by ditac (**Table of Contents**, **List of Figures**, **Chapter**, **Appendix**, etc) are available in English (en), French (fr), German (de), Spanish (es), etc. Now let's suppose that you are routinely authoring Portuguese documents and that you want ditac to also support this language.

Procedure

1. Go to the `ditac_install_dir/xsl/common/messages/` directory.

```
~$ cd /opt/ditac/xsl/common/messages/
```

2. Copy `en.xml` to `pt.xml`.

Note that "pt" is the ISO 639-1 two-letter code of the Portuguese language.

Country variants of a language are supported too. Example: `pt-BR` (Brazilian Portuguese). However, when this is the case, make sure that the name of the file containing your messages use lower-case characters. Example: `pt-br.xml` should be fine, while `pt-BR.xml` or `pt_br.xml` would not work.

```
/opt/ditac/xsl/common/messages$ cp en.xml pt.xml
```

3. Open `pt.xml` in a text or XML editor and translate to Portuguese all the messages found in this file.

```
<?xml version="1.0" encoding="UTF-8"?>
<messages xml:lang="pt">
  <!-- Task sections -->
  <message name="prereq">Pré-requisito</message>
  ...
```

For some languages, like CJK languages, you'll have to insert variable `%{N}` in the localized text corresponding to numbered elements (Chapter, Appendix, Table, Figure, etc). This variable is replaced by the number of the element.

Japanese example: excerpts of a possible `ditac_install_dir/xsl/common/messages/ja.xml`:

```
<message name="chapter">#%{N}#</message>
```

For the first chapter of the document, this gives "`#1#`", which means "The 1 Chapter".

4. Open `ditac_install_dir/xsl/common/commonUtil.xsl` in a text or XML editor and add string 'pt' at the end of the `messageFileNames` list:

```
<!-- localize ===== -->

<xsl:param name="messageFileNames" select="'en', 'fr', 'de', 'es', 'pt'"/>
```

5. When done, please send us (ditac-support@xmlmind.com) your translation (e.g. `pt.xml`) so we can add your contribution to the distribution of XMLmind DITA Converter.

Index

A

add-copiable-links, parameter, 30
 -addindex, option, 17
 add-index-toc, parameter, 31
 add-toc-root, parameter, 36
 -ahf, option, 17
 AHF, XSL-FO processor, 2, 7, 17, 18, 117
 -ahfconf, option, 18
 Antenna House Formatter. *See* AHF, XSL-FO processor;
 FOP, XSL-FO processor
 Apache FOP. *See* FOP, XSL-FO processor
 appendix-number-format, parameter, 24
 audio, 65
 audio, element, 66
 -automap, option, 20

B

-backmatter, option, 17
 base-font-size, parameter, 43
 body-bottom-margin, parameter, 43
 body-font-family, parameter, 43
 body-start-indent, parameter, 43
 body-top-margin, parameter, 44
 {{break}}, page header/footer variable, 53

C

-c, option, 14
 cause-number-format, parameter, 24
 center, parameter, 24
 chain-pages, parameter, 31
 chain-topics, parameter, 31. *See also* ignore-
 navigation-links, parameter
 changes
 bars, 116
 highlighting, 115
 {{chapter-title}}, page header/footer variable,
 52
 .chm, filename extension, 7. *See also* HTML
 Help, output format
 chmBasename, parameter, 41
 choice-bullets, parameter, 44
 -chunk, option, 14
 coderef, implementation specificity, 113
 cover-image, parameter, 42
 CSS, custom, 70
 css, parameter, 32
 cssResourceName, parameter, 32

custom-css, parameter, 32, 71

D

default-table-width, parameter, 32
 DITAC_PLUGIN_DIR, environment variable,
 23
 ditac.options, options file, 3, 20
 ditacListsURI, parameter, 24
 ditac plug-in, 4, 19, 22
 DITA specialization, 73
 DITAVAL, conditional processing, 16, 115,
 116
 .doc, filename extension, 7. *See also* RTF,
 output format
 {{document-date}}, page header/footer
 variable, 52
 {{document-title}}, page header/footer
 variable, 52
 .docx, filename extension, 8. *See also* Office
 Open XML, output format
 docx, output format name. *See* Office Open
 XML, output format
 -dryrun, option, 20

E

Eclipse Help, output format, 5, 10, 12, 22, 70
 eclipsehelp, output format name. *See* Eclipse
 Help, output format
 .epub, filename extension, 7. *See also* EPUB 2,
 output format
 epub, output format name. *See* EPUB 2, output
 format
 EPUB 2, output format, 5, 7, 10, 13, 22, 25, 70
 epub2-compatible, parameter, 43
 EPUB 3, output format, 5, 10, 13, 13, 22, 25,
 43, 43, 62, 64, 70
 epub3, output format name. *See* EPUB 3,
 output format
 epub-identifier, parameter, 43
 equation-block-equation-width, parameter, 44
 equation-block-number-width, parameter, 44
 equation-number-after, parameter, 24
 equation-number-before, parameter, 25
 -errout, option, 20
 extended-toc, parameter, 25
 external-href-after, parameter, 44
 external-href-before, parameter, 44
 external-link-icon-height, parameter, 33
 external-link-icon-name, parameter, 33
 external-link-icon-width, parameter, 33

external-resource-base, parameter, 25

F

- f, option, 15
- filter, option, 16, 115, 116
- fo, output format name. *See* XSL-FO, output format
- foconverter, option, 18
- footer-center, parameter, 44
- footer-center-width, parameter, 45
- footer-height, parameter, 45
- footer-left, parameter, 45
- footer-left-width, parameter, 45
- footer-right, parameter, 45
- footer-right-width, parameter, 45
- footer-separator, parameter, 45
- fop, option, 18
- FOP, XSL-FO processor, 2, 4, 7, 7, 18, 18, 117
- fopconf, option, 18
- foProcessor, parameter, 44
- format, option, 15
- format-to-type, parameter, 33
- frontmatter, option, 16

G

- Generated messages. *See* Translation
- generator-info, parameter, 33
- glossref, implementation specificity, 118

H

- HDITA, 94
- header-center, parameter, 45
- header-center-width, parameter, 46
- header-height, parameter, 46
- header-left, parameter, 46
- header-left-width, parameter, 46
- header-right, parameter, 46
- header-right-width, parameter, 46
- header-separator, parameter, 46
- hhc, option, 19
- hhc-basename, parameter, 41
- hhpBasename, parameter, 41
- hhp-template, parameter, 41
- hhx-basename, parameter, 42
- highlight-source, parameter, 25
- .htm, filename extension, 7. *See also* XHTML 1.0, output format
- .html, filename extension, 7. *See also* XHTML 1.0, output format
- html, output format name. *See* HTML 4.01, output format

- HTML 4.01, output format, 5, 10, 10, 22, 70
- HTML Help, output format, 5, 7, 10, 11, 22, 56, 70

- htmlhelp, output format name. *See* HTML Help, output format
- hyphenate, parameter, 46

I

- i, option, 15, 19
- ignore-navigation-links, parameter, 33. *See also* chain-topics, parameter
- ignoreoptionsfile, option, 20
- {{image(URI)}}, page header/footer variable, 53
- imageconverter, option, 19
- imagemap, 49
- images, option, 15
- index, option, 16
- index-column-gap, parameter, 46
- index-range-separator, parameter, 25

J

- Java Help, output format, 56
- javascripts, parameter, 33
- justified, parameter, 46

K

- keepfo, option, 20

L

- lang, option, 17
- Lightweight DITA, 94
- Lightweight DITA support, 66, 67
- link-auto-text, parameter, 26
- link-bullet, parameter, 47
- Localization. *See* Translation
- LwDITA. *See* Lightweight DITA; Lightweight DITA support

M

- Markdown, 14, 94
- mark-external-links, parameter, 34
- mark-important-steps, parameter, 26
- MathJax, 34, 34
- mathjax, parameter, 34
- mathjax-url, parameter, 34
- MathML, 34, 63
- MDITA, 14, 94
- menucascade-separator, parameter, 47

N

navigation-icon-height, parameter, 34
 navigation-icon-suffix, parameter, 35
 navigation-icon-width, parameter, 35
 note-icon-height, parameter, 47
 note-icon-list, parameter, 26
 note-icon-suffix, parameter, 47
 note-icon-width, parameter, 47
 number, parameter, 9, 26
 number-separator1, parameter, 26
 number-separator2, parameter, 26
 number-toc-entries, parameter, 36

O

-o, option, 17
 object, element, 65, 66, 68
 .odt, filename extension, 8. *See also*
 OpenOffice, output format
 odt, output format name. *See* OpenOffice,
 output format
 Office Open XML, output format, 5, 8, 8, 10,
 22, 71
 OpenOffice, output format, 5, 8, 8, 10, 22, 71
 -options, option, 17
 ordered list, numbering, 56
 out of memory error, 21
 outputclass, attribute, 25
 outputclass, implementation specificity, 58, 60

P

-p, option, 14
 page-bottom-margin, parameter, 47
 pagebreak, processing-instruction, 43
 {{page-count}}, page header/footer variable,
 53
 page-height, parameter, 47
 page-inner-margin, parameter, 48
 {{page-number}}, page header/footer variable,
 53
 page-orientation, parameter, 48
 page-outer-margin, parameter, 48
 page-ref-after, parameter, 48
 page-ref-before, parameter, 48
 {{page-sequence}}, page header/footer
 variable, 53, 54
 page-top-margin, parameter, 48
 page-width, parameter, 48
 paper-type, parameter, 48
 -param, option, 14
 Parameters. *See* XSLT stylesheets parameters
 part-number-format, parameter, 27

.pdf, filename extension, 7. *See also* PDF,
 output format
 PDF, output format, 5, 7, 7, 10, 22, 71
 pdf, output format name. *See* PDF, output
 format
 pdf-outline, parameter, 49
 -plugin, option, 19
 plug-in, 22. *See also* ditac plug-in
 plugin-id, parameter, 42
 plugin-index-basename, 42
 plugin-name, parameter, 42
 plugin-provider, parameter, 42
 plugin-toc-basename, parameter, 42
 plugin-version, parameter, 42
 PostScript, output format, 5, 7, 7, 10, 22, 71
 prepend-chapter-to-section-number, parameter,
 27
 -preprocess, option, 20, 77
 .ps, filename extension, 7. *See also* PostScript,
 output format
 ps, output format name. *See* PostScript, output
 format

R

-r, option, 15
 remedy-number-format, parameter, 27
 RenderX XEP. *See* XEP, XSL-FO processor
 -resourcehandler, option, 15, 19
 -resources, option, 15
 .rtf, filename extension, 7. *See also* RTF,
 output format
 RTF, output format, 5, 7, 8, 10, 22, 71
 rtf, output format name. *See* RTF, output
 format

S

screen-resolution, parameter, 35
 {{section1-title}}, page header/footer variable,
 53
 show-draft-comments, parameter, 27
 show-external-links, parameter, 49
 show-imagemap-links, parameter, 49
 show-link-page, parameter, 49
 show-xref-page, parameter, 49
 Subject scheme maps, 16, 16, 20, 113
 SVG, 62
 syntax highlighting, 25, 58, 60

T

-t, option, 14, 72
 table, background color, 57

TeX/LaTeX math, 64
 title-after, parameter, 27
 title-color, parameter, 50
 title-font-family, parameter, 50
 title-page, parameter, 27
 title-prefix-separator1, parameter, 28
 -toc, option, 8, 16
 {{topic-title}}, page header/footer variable, 53, 54
 Translation, 119
 troubleSolution-number-format, parameter, 27
 two-sided, parameter, 50

U

ul-li-bullets, parameter, 50
 unordered-step-bullets, parameter, 50
 use-note-icon, parameter, 28

V

-v, option, 9, 17
 -validate, option, 20
 -version, option, 20
 video, 66, 68
 video, element, 67
 -vv, option, 17
 -vvv, option, 17

W

watermark, parameter, 50
 watermark-image, parameter, 28
 Web Help, output format, 5, 5, 10, 11, 22, 22, 70
 webhelp, output format name. *See* Web Help, output format
 Web Help 5, output format, 10, 11, 62, 64, 65
 webhelp5, output format name. *See* Web Help 5, output format
 whc-index-basename, parameter, 41
 wh-collapse-toc, parameter, 37
 wh---CSS_VAR_NAME, parameter, 36
 whc-toc-basename, parameter, 41
 wh-favicon, parameter, 37
 wh-index-numbers, parameter, 37
 wh-inherit-font-and-colors, parameter, 37
 wh-jquery, parameter, 37
 wh-layout, parameter, 38
 wh-local-jquery, parameter, 38
 wh-responsive-ui, parameter, 38
 wh-ui-language, parameter, 38
 wh-user-css, parameter, 39
 wh-user-footer, parameter, 39

wh-user-header, parameter, 39
 wh-user-resources, parameter, 40
 wh-use-stemming, parameter, 38
 .wml, filename extension, 8. *See also*
 WordprocessingML, output format
 wml, output format name. *See*
 WordprocessingML, output format
 WordprocessingML, output format, 5, 8, 8, 10, 22, 71

X

XDITA, 94
 -xep, option, 19
 XEP, XSL-FO processor, 2, 7, 16, 19, 21, 117
 -xfc, option, 19
 XFC, XSL-FO Converter, 9
 XFC, XSL-FO processor, 3, 8, 19, 51, 56, 117
 xfc-render-as-table, parameter, 51
 .xhtml, filename extension, 7. *See also*
 XHTML 1.0, output format
 xhtml, output format name. *See* XHTML 1.0, output format
 XHTML 1.0, output format, 5, 7, 9, 10, 22, 70
 XHTML 1.1, output format, 5, 10, 10, 22, 70
 xhtml1.1, output format name. *See* XHTML 1.1, output format
 XHTML 5, output format, 5, 10, 10, 22, 62, 64, 65, 70
 xhtml5, output format name. *See* XHTML 5, output format
 xhtml-mime-type, parameter, 35
 .xml, filename extension, 8. *See also*
 WordprocessingML, output format
 XML catalog, 73
 XMLmind XSL-FO Converter. *See* XFC, XSL-FO processor
 -Xmx, Java option, 21
 xref-auto-text, parameter, 29
 XSL-FO, output format, 10
 xsl-resources-directory, parameter, 29
 -xslt, option, 14
 XSLT stylesheets parameters, 24

Y

YouTube, 68